
hera_sim Documentation

Release 0.0.0

HERA-Team

Feb 26, 2021

CONTENTS

1	Contents	3
2	Indices and tables	83
	Python Module Index	85
	Index	87

hera_sim is a simple simulator that generates instrumental effects and applies them to visibilities.

CONTENTS

1.1 Installation

1.1.1 Requirements

Requires:

- numpy
- scipy
- aipy
- pyuvdata

Then, at the command line, navigate to the `hera_sim` repo/directory, and:

```
pip install .
```

If developing, from the top-level directory do:

```
pip install -e .
```

1.2 Tutorials and FAQs

The following introductory tutorial will help you get started with `hera_sim`:

1.2.1 Tour of `hera_sim`

This notebook briefly introduces some of the effects that can be modeled with `hera_sim`.

```
[1]: %matplotlib notebook
import aipy, uvtools
import numpy as np
import pylab as plt
```

```
[2]: from hera_sim import foregrounds, noise, sigchain, rfi
/home/bobby/HERA/dev/fix_tutorial/hera_sim/hera_sim/visibilities/__init__.py:27:_
  UserWarning: PRISim failed to import.
  warnings.warn("PRISim failed to import.")
```

(continues on next page)

(continued from previous page)

```
/home/bobby/HERA/dev/fix_tutorial/hera_sim/hera_sim/visibilities/__init__.py:33:_
  ↵UserWarning: VisGPU failed to import.
    warnings.warn("VisGPU failed to import.")
/home/bobby/HERA/dev/fix_tutorial/hera_sim/hera_sim/__init__.py:36: FutureWarning:
In the next major release, all HERA-specific variables will be removed from the_
  ↵codebase. The following variables will need to be accessed through new class-like_
  ↵structures to be introduced in the next major release:

noise.HERA_Tsky_mdl
noise.HERA_BEAM_POLY
sigchain.HERA_NRAO_BANDPASS
rfi.HERA_RFI_STATIONS

Additionally, the next major release will involve modifications to the package's API,_
  ↵which move toward a regularization of the way in which hera_sim methods are_
  ↵interfaced with; in particular, changes will be made such that the Simulator class_
  ↵is the most intuitive way of interfacing with the hera_sim package features.

FutureWarning)
```

```
[3]: fqs = np.linspace(.1,.2,1024,endpoint=False)
lsts = np.linspace(0,2*np.pi,10000, endpoint=False)
times = lsts / (2*np.pi) * aipy.const.sidereal_day
bl_len_ns = np.array([30., 0, 0])
```

Foregrounds

Diffuse Foregrounds

```
[4]: Tsky_mdl = noise.HERA_Tsky_mdl['xx']
vis_fg_diffuse = foregrounds.diffuse_foreground(lst, fqs, bl_len_ns, Tsky_mdl)
```

```
[5]: MX, DRNG = 2.5, 3
plt.figure()
plt.subplot(211); uvtools.plot.waterfall(vis_fg_diffuse, mode='log', mx=MX,_
  ↵drng=DRNG); plt.colorbar(); plt.ylim(0,4000)
plt.subplot(212); uvtools.plot.waterfall(vis_fg_diffuse, mode='phs'); plt.colorbar();_
  ↵plt.ylim(0,4000)
plt.show()

<IPython.core.display.Javascript object>
<IPython.core.display.HTML object>
```

Point-Source Foregrounds

```
[6]: vis_fg_pntsrc = foregrounds.pntsrc_foreground(lst, fqs, bl_len_ns, nsrcs=200)
```

```
[7]: plt.figure()
plt.subplot(211); uvtools.plot.waterfall(vis_fg_pntsrc, mode='log', mx=MX, drng=DRNG);
  ↵ plt.colorbar(); plt.ylim(0,4000)
plt.subplot(212); uvtools.plot.waterfall(vis_fg_pntsrc, mode='phs'); plt.colorbar();_
  ↵plt.ylim(0,4000)
```

(continues on next page)

(continued from previous page)

```
plt.show()

<IPython.core.display.Javascript object>
<IPython.core.display.HTML object>

/home/bobby/anaconda3/envs/fix_tutorial/lib/python3.7/site-packages/uvtools/plot.py:
→40: RuntimeWarning: divide by zero encountered in log10
    data = np.log10(data)
```

Diffuse and Point-Source Foregrounds

```
[8]: vis_fg = vis_fg_diffuse + vis_fg_pntsrc
```

```
[9]: plt.figure()
plt.subplot(211); uvtools.plot.waterfall(vis_fg, mode='log', mx=MX, drng=DRNG); plt.
→colorbar(); plt.ylim(0,4000)
plt.subplot(212); uvtools.plot.waterfall(vis_fg, mode='phs'); plt.colorbar(); plt.
→ylim(0,4000)
plt.show()

<IPython.core.display.Javascript object>
<IPython.core.display.HTML object>
```

Noise

```
[10]: tsky = noise.resample_Tsky(fqs,lsts,Tsky_mdl=noise.HERA_Tsky_mdl['xx'])
t_rx = 150.
omega_p = noise.bm_poly_to_omega_p(fqs)
nos_jy = noise.sky_noise_jy(tsky + t_rx, fqs, lsts, omega_p)
```

```
[11]: plt.figure()
plt.subplot(211); uvtools.plot.waterfall(nos_jy, mode='log', mx=MX, drng=DRNG); plt.
→colorbar() #; plt.ylim(0,4000)
plt.subplot(212); uvtools.plot.waterfall(nos_jy, mode='phs'); plt.colorbar() #; plt.
→ylim(0,4000)
plt.show()

<IPython.core.display.Javascript object>
<IPython.core.display.HTML object>
```

```
[12]: vis_fg_nos = vis_fg + nos_jy
```

```
[13]: plt.figure()
plt.subplot(211); uvtools.plot.waterfall(vis_fg_nos, mode='log', mx=MX, drng=DRNG); ▾
→plt.colorbar(); plt.ylim(0,4000)
plt.subplot(212); uvtools.plot.waterfall(vis_fg_nos, mode='phs'); plt.colorbar(); plt.
→ylim(0,4000)
plt.show()

<IPython.core.display.Javascript object>
```

```
<IPython.core.display.HTML object>
```

RFI

```
[14]: rfi1 = rfi.rfi_stations(fqs, lsts)
rfi2 = rfi.rfi_impulse(fqs, lsts, chance=.02)
rfi3 = rfi.rfi_scatter(fqs, lsts, chance=.001)
rfi_all = rfi1 + rfi2 + rfi3

[15]: plt.figure()
plt.subplot(211); uvtools.plot.waterfall(rfi_all, mode='log', mx=MX, drng=DRNG); plt.
    ~colorbar(); plt.ylim(0,4000)
plt.subplot(212); uvtools.plot.waterfall(rfi_all, mode='phs'); plt.colorbar(); plt.
    ~ylim(0,4000)
plt.show()

<IPython.core.display.Javascript object>
<IPython.core.display.HTML object>

[16]: vis_fg_nos_rfi = vis_fg_nos + rfi_all

[17]: plt.figure()
plt.subplot(211); uvtools.plot.waterfall(vis_fg_nos_rfi, mode='log', mx=MX, ~
    ~drng=DRNG); plt.colorbar(); plt.ylim(0,4000)
plt.subplot(212); uvtools.plot.waterfall(vis_fg_nos_rfi, mode='phs'); plt.colorbar(); ~
    ~plt.ylim(0,4000)
plt.show()

<IPython.core.display.Javascript object>
<IPython.core.display.HTML object>
```

Gains

```
[18]: g = sigchain.gen_gains(fqs, [1,2,3])
plt.figure()
for i in g: plt.plot(fqs, np.abs(g[i]), label=str(i))
plt.legend(); plt.show()
gainscale = np.average([np.median(np.abs(g[i])) for i in g])
MXG = MX + np.log10(gainscale)

<IPython.core.display.Javascript object>
<IPython.core.display.HTML object>
```

```
[19]: vis_total = sigchain.apply_gains(vis_fg_nos_rfi, g, (1,2))
plt.figure()
plt.subplot(211); uvtools.plot.waterfall(vis_total, mode='log', mx=MXG, drng=DRNG); ~
    ~plt.colorbar(); plt.ylim(0,4000)
plt.subplot(212); uvtools.plot.waterfall(vis_total, mode='phs'); plt.colorbar(); plt.
    ~ylim(0,4000)
plt.show()
```

```
<IPython.core.display.Javascript object>
<IPython.core.display.HTML object>
```

Crosstalk

```
[20]: xtalk = sigchain.gen_whitenoise_xtalk(fqs)
vis_xtalk = sigchain.apply_xtalk(vis_fg_nos_rfi, xtalk)
vis_xtalk = sigchain.apply_gains(vis_xtalk, g, (1,2))
plt.figure()
plt.subplot(211); uvtools.plot.waterfall(vis_xtalk, mode='log', mx=MXG, drng=DRNG);
    ↪plt.colorbar(); plt.ylim(0,4000)
plt.subplot(212); uvtools.plot.waterfall(vis_xtalk, mode='phs'); plt.colorbar(); plt.
    ↪ylim(0,4000)
plt.show()

<IPython.core.display.Javascript object>
<IPython.core.display.HTML object>
```

[]:

The following tutorial will help you learn how use the `Simulator` class:

1.2.2 The Simulator Class

The most convenient way to use `hera_sim` is to use the `Simulator` class, which builds in all the primary functionality of the `hera_sim` package in an easy-to-use interface, and adds the ability to consistently write all produced effects into a `pyuvdata.UVData` object (and to file).

What follows is a quick tour of the main functionality this provides.

Setup

```
[1]: %matplotlib inline
import os
import matplotlib.pyplot as plt
import numpy as np
import astropy.units as u

import hera_sim
import uvtools

from hera_sim.simulate import Simulator
from hera_sim.noise import HERA_Tsky_mdl
from hera_sim.data import DATA_PATH
from hera_sim.interpolators import Beam

/home/bobby/HERA/dev/fix_tutorial/hera_sim/hera_sim/visibilities/__init__.py:27:_
    ↪UserWarning: PRISim failed to import.
    warnings.warn("PRISim failed to import.")
/home/bobby/HERA/dev/fix_tutorial/hera_sim/hera_sim/visibilities/__init__.py:33:_
    ↪UserWarning: VisGPU failed to import.
    warnings.warn("VisGPU failed to import.")
```

(continues on next page)

(continued from previous page)

```
/home/bobby/HERA/dev/fix_tutorial/hera_sim/hera_sim/__init__.py:36: FutureWarning:  
In the next major release, all HERA-specific variables will be removed from the  
→codebase. The following variables will need to be accessed through new class-like  
→structures to be introduced in the next major release:
```

```
noise.HERA_Tsky_mdl  
noise.HERA_BEAM_POLY  
sigchain.HERA_NRAO_BANDPASS  
rfi.HERA_RFI_STATIONS
```

Additionally, the next major release will involve modifications to the package's API,
→which move toward a regularization of the way in which hera_sim methods are
→interfaced with; in particular, changes will be made such that the Simulator class
→is the most intuitive way of interfacing with the hera_sim package features.
FutureWarning)

The Simulator Class

The Simulator class holds everything required to generate and do basic analysis on a simulation. It can be instantiated by submitting any one of the following: a filename pointing to an existing simulation in uvfits, uvh5 or miriad format; a UVData object, or a set of keyword arguments which are passed to the hera_sim.io.empty_uvdata function. Any keyword arguments passed to the Simulator initializer are passed directly to the hera_sim.io.empty_uvdata, and those are in turn passed directly to the pyuvsim.simsetup.initialize_uvdata_from_keywords function, so that setting up a simulation object is relatively straightforward. The default parameter values for the empty_uvdata function are all set to None, but are given default values to show a suggested minimal set of parameters necessary to initialize a UVData object (and, in turn, a Simulator object):

```
hera_sim.io.empty_uvdata(  
    Ntimes=None,  
    start_time=None,  
    integration_time=None,  
    Nfreqs=None,  
    start_freq=None,  
    channel_width=None,  
    array_layout=None,  
    **kwargs,  
)
```

If you are curious about the full set of parameters that may be used to initialize a UVData object, then please see the documentation for the pyuvsim.simsetup.initialize_uvdata_from_keywords function.

To get us started, let's make a Simulator object with 100 frequency channels spanning from 100 to 200 MHz, a half-hour of observing time with an H1C-appropriate integration time of 10.7 seconds, and a 7-element hexagonal array.

```
[2]: # first, generate the array. this is returned as a dict  
# with antenna numbers as keys and ENU positions as values  
ants = hera_sim.antpos.hex_array(2, split_core=False, outriggers=0)  
  
# for clarity about some timing parameters  
start_time = 2458115.9 # JD  
integration_time = 10.7 # seconds  
Ntimes = int(30 * u.min.to("s") / integration_time)
```

(continues on next page)

(continued from previous page)

```
sim = Simulator(
    Nfreqs=100,
    start_freq=1e8,
    bandwidth=1e8,
    Ntimes=Ntimes,
    start_time=start_time,
    integration_time=integration_time,
    array_layout=ants
)
```

The Simulator class adds some attributes for conveniently accessing metadata:

You can retrieve the frequencies (in GHz) with the freqs attribute. (sim.freqs)

You can retrieve the LSTs (in radians) with the lsts attribute. (sim.lsts)

You can retrieve the antenna array with the antpos attribute. (sim.antpos)

```
[3]: sim.freqs
[3]: array([0.1 , 0.101, 0.102, 0.103, 0.104, 0.105, 0.106, 0.107, 0.108,
       0.109, 0.11 , 0.111, 0.112, 0.113, 0.114, 0.115, 0.116, 0.117,
       0.118, 0.119, 0.12 , 0.121, 0.122, 0.123, 0.124, 0.125, 0.126,
       0.127, 0.128, 0.129, 0.13 , 0.131, 0.132, 0.133, 0.134, 0.135,
       0.136, 0.137, 0.138, 0.139, 0.14 , 0.141, 0.142, 0.143, 0.144,
       0.145, 0.146, 0.147, 0.148, 0.149, 0.15 , 0.151, 0.152, 0.153,
       0.154, 0.155, 0.156, 0.157, 0.158, 0.159, 0.16 , 0.161, 0.162,
       0.163, 0.164, 0.165, 0.166, 0.167, 0.168, 0.169, 0.17 , 0.171,
       0.172, 0.173, 0.174, 0.175, 0.176, 0.177, 0.178, 0.179, 0.18 ,
       0.181, 0.182, 0.183, 0.184, 0.185, 0.186, 0.187, 0.188, 0.189,
       0.19 , 0.191, 0.192, 0.193, 0.194, 0.195, 0.196, 0.197, 0.198,
       0.199])
```

```
[4]: sim.lsts
[4]: array([4.58108965, 4.58186991, 4.58265017, 4.58343042, 4.58421068,
       4.58499094, 4.58577119, 4.58655145, 4.58733171, 4.58811196,
       4.58889222, 4.58967247, 4.59045273, 4.59123299, 4.59201324,
       4.5927935 , 4.59357376, 4.59435401, 4.59513427, 4.59591452,
       4.59669478, 4.59747504, 4.59825529, 4.59903555, 4.59981581,
       4.60059606, 4.60137632, 4.60215657, 4.60293683, 4.60371709,
       4.60449734, 4.6052776 , 4.60605786, 4.60683811, 4.60761837,
       4.60839863, 4.60917888, 4.60995914, 4.6107394 , 4.61151965,
       4.61229991, 4.61308017, 4.61386042, 4.61464068, 4.61542093,
       4.61620119, 4.61698145, 4.6177617 , 4.61854196, 4.61932222,
       4.62010247, 4.62088273, 4.62166299, 4.62244324, 4.6232235 ,
       4.62400375, 4.62478401, 4.62556427, 4.62634452, 4.62712478,
       4.62790503, 4.62868529, 4.62946555, 4.6302458 , 4.63102606,
       4.63180632, 4.63258657, 4.63336683, 4.63414709, 4.63492734,
       4.6357076 , 4.63648786, 4.63726811, 4.63804837, 4.63882863,
       4.63960888, 4.64038914, 4.64116939, 4.64194965, 4.64272991,
       4.64351016, 4.64429042, 4.64507068, 4.64585093, 4.64663119,
       4.64741145, 4.6481917 , 4.64897196, 4.64975221, 4.65053247,
       4.65131273, 4.65209298, 4.65287324, 4.65365349, 4.65443375,
       4.65521401, 4.65599426, 4.65677452, 4.65755478, 4.65833503,
```

(continues on next page)

(continued from previous page)


```
4.65911529, 4.65989555, 4.6606758 , 4.66145606, 4.66223632,
4.66301657, 4.66379683, 4.66457709, 4.66535734, 4.6661376 ,
4.66691785, 4.66769811, 4.66847837, 4.66925862, 4.67003888,
4.67081914, 4.67159939, 4.67237965, 4.67315991, 4.67394016,
4.67472042, 4.67550068, 4.67628093, 4.67706119, 4.67784144,
4.6786217 , 4.67940196, 4.68018221, 4.68096247, 4.68174272,
4.68252298, 4.68330324, 4.68408349, 4.68486375, 4.68564401,
4.68642426, 4.68720452, 4.68798478, 4.68876503, 4.68954529,
4.69032555, 4.6911058 , 4.69188606, 4.69266631, 4.69344657,
4.69422683, 4.69500708, 4.69578734, 4.6965676 , 4.69734785,
4.69812811, 4.69890837, 4.69968862, 4.70046888, 4.70124914,
4.70202939, 4.70280965, 4.7035899 , 4.70437016, 4.70515042,
4.70593067, 4.70671093, 4.70749118, 4.70827144, 4.7090517 ,
4.70983195, 4.71061221, 4.71139247])
```

```
[5]: sim.antpos
```

```
[5]: {0: array([-7.30000000e+00, 1.26439709e+01, -4.36185665e-09]),
 1: array([ 7.30000000e+00, 1.26439709e+01, -3.99203159e-09]),
 2: array([-1.46000000e+01, 6.98581573e-09, -4.65185394e-09]),
 3: array([ 0.00000000e+00, 7.20559015e-09, -4.28202888e-09]),
 4: array([ 1.46000000e+01, 7.42536457e-09, -3.91220382e-09]),
 5: array([-7.30000000e+00, -1.26439709e+01, -4.57202631e-09]),
 6: array([ 7.30000000e+00, -1.26439709e+01, -4.20220125e-09])}
```

You can also generate a plot of the array layout using the `plot_array` method:

```
[6]: fig = sim.plot_array()
plt.show()
```



The `data` attribute can be used to access the `UVData` object used to store the simulated data and metadata:

```
[7]: from pyuvdata import UVData
isinstance(sim.data, UVData)

[7]: True
```

We'll use a standard waterfall plot throughout the notebook to show the progress of the simulation:

```
[8]: def waterfall(
    vis, freqs=sim.freqs * 1e3, lsts=sim.lsts,
    vmax=None, vrange=None, title=None,
):
    """
    A wrapper around the uvtools' waterfall function providing some
    extra labelling and plot adjustment.
    """
    fig, ax = plt.subplots(
        2, 1, sharex=True, sharey=True, figsize=(12, 10)
    )

    if title is not None:
        ax[0].set_title(title, fontsize=12)
```

(continues on next page)

(continued from previous page)

```
plt.sca(ax[0])
uvtools.plot.waterfall(
    vis, mode='log', mx=vmax, drng=vrangle,
    extent=(freqs.min(), freqs.max(), lsts.min(), lsts.max())
)
plt.colorbar(label=r'log$_{10}$(Vis/Jy)')
plt.ylabel("LST", fontsize=12)

plt.sca(ax[1])
uvtools.plot.waterfall(
    vis,
    mode='phs',
    cmap='twilight',
    extent=(freqs.min(), freqs.max(), lsts.min(), lsts.max())
)
plt.colorbar(label='Phase [rad]')
plt.xlabel("Frequency [MHz]", fontsize=12)
plt.ylabel("LST", fontsize=12)
```

Adding Effects

Effects may be added to a simulation by using the `add` method. This method takes one argument and variable keyword arguments: the required argument `component` may be either a string identifying the name of a `hera_sim` class (or an alias thereof, see below), or a callable object that has either `lsts` or `freqs` (or both) as a parameter(s) and returns an object with shape (`lsts.size`, `freqs.size`) or (`freqs.size`,) (granted, the Simulator does not do a check on the input parameters or the shape of returned values, but passing a callable object that returns something incorrectly shaped will likely result in an exception being raised). Let's walk through an example.

A Simple Example

Let's begin by simulating diffuse foregrounds. To do this, we'll need to specify a sky temperature model and a beam area interpolator object (or array of values corresponding to a frequency-dependent beam size). Let's use the sky temperature model and beam polynomial fit for H1C:

```
[9]: from hera_sim.interpolators import Beam
from hera_sim.noise import HERA_Tsky_mdl
from hera_sim.data import DATA_PATH


# HERA_Tsky_mdl is a dictionary with keys 'xx' and 'yy'
Tsky_mdl = HERA_Tsky_mdl['xx']

# there are useful files in the data directory, with this being one
beamfile = os.path.join(DATA_PATH, "HERA_H1C_BEAM_POLY.npy")

# we can make a beam interpolation object from a path to a .npy file
omega_p = Beam(beamfile)

# now to add the foregrounds
sim.add("diffuse_foreground", Tsky_mdl=Tsky_mdl, omega_p=omega_p)
```

```
[10]: # let's check out the data for the (0,1) baseline
vis = sim.data.get_data((0,1,'xx'))
waterfall(vis, title='Simulated Diffuse Foregrounds')
```



Now, whenever an effect is simulated using the `add` method, that effect (and any non-default optional parameters used) is logged: a note of what was simulated is put into the object's history, and the information is also stored in a hidden attribute `_components`.

```
[11]: print(sim.data.history)

hera_sim v1.0.0: Added DiffuseForeground using kwargs:
Tsky_mdl = <hera_sim.interpolators.Tsky object at 0x7fb870d28b50>
omega_p = <hera_sim.interpolators.Beam object at 0x7fb86dbd3390>
```



```
[12]: sim._components
```

```
[12]: {'diffuse_foreground': {'Tsky_mdl': <hera_sim.interpolators.Tsky at 0x7fb870d28b50>,
 'omega_p': <hera_sim.interpolators.Beam at 0x7fb86dbd3390>}}
```


Note that the actual visibility simulated is not cached, but rather the parameters necessary for recreating are saved and

can be used to later re-simulate the effect. Now, the diffuse foreground simulator uses a random number generator, so if we want to ensure repeatability, we have to make sure it's seeded in some repeatable way...

```
[13]: # refresh the simulation
# this zeros the data array, resets the history, and clears the _components dictionary
sim.refresh()

from hera_sim.foregrounds import DiffuseForeground
# now let's seed by redundant group
sim.add(DiffuseForeground, Tsky_mdl=Tsky_mdl, omega_p=omega_p, seed_mode="redundantly
    ↵")
```

```
[14]: # and let's take a look
vis = sim.data.get_data((0,1,'xx'))
waterfall(vis, title='Simulated Diffuse Foregrounds')
```



```
[15]: # as for the history
print(sim.data.history)
```

```
hera_sim v1.0.0: Added DiffuseForeground using kwargs:
Tsky_mdl = <hera_sim.interpolators.Tsky object at 0x7fb870d28b50>
omega_p = <hera_sim.interpolators.Beam object at 0x7fb86dbd3390>
seed_mode = redundantly
```

```
[16]: # and the _components
sim._components

[16]: {hera_sim.foregrounds.DiffuseForeground: {'Tsky_mdl': <hera_sim.interpolators.Tsky at 0x7fb870d28b50>,
                                                'omega_p': <hera_sim.interpolators.Beam at 0x7fb86dbd3390>,
                                                'seed_mode': 'redundantly'}}
```

Note that using the DiffuseForeground class to simulate the effect caused the Simulator to log the component using the class itself as the key.

```
[17]: # we can even re-simulate the effect
vis_copy = sim.get(DiffuseForeground, ant1=0, ant2=1, pol='xx')
np.all(np.isclose(vis, vis_copy))

[17]: True
```

```
[18]: # but do baselines within a redundant group agree?
for reds in sim._get_reds():
    red_grp = [sim.data.baseline_to_antnums(red) for red in reds]
    print(list(red_grp))

[(0, 0), (1, 1), (2, 2), (3, 3), (4, 4), (5, 5), (6, 6)]
[(0, 1), (2, 3), (3, 4), (5, 6)]
[(0, 2), (1, 3), (3, 5), (4, 6)]
[(0, 3), (1, 4), (2, 5), (3, 6)]
[(0, 4), (2, 6)]
[(0, 5), (1, 6)]
[(0, 6)]
[(1, 2), (4, 5)]
[(1, 5)]
[(2, 4)]
```

```
[19]: np.all(
    np.isclose(sim.data.get_data(0,1), sim.data.get_data(2,3))
)

[19]: True
```

A final note on this: when the seed_mode parameter is set to "redundantly", a seed is generated for each redundant group, and that seed is used to ensure that each baseline within a redundant group observes the same realization of the effect; the only other mode that's currently supported is "once", which just seeds the random number generator once before any effects are simulated.

Filtering Effects

The `add` method also allows for an optional keyword argument `vis_filter`. This may be an iterable of arbitrary length, or an iterable of keys of various lengths. This is still under-developed and may have a different implementation in the near future, so this section will not go into any detail about how it works.

As a quick example, let's choose our filter so that only the '`xx`' polarization for the baseline `(0, 1)` (and its conjugate) is simulated. To check that it works, we'll test that the antennas' autoc

```
[20]: sim.refresh()
sim.add("noiselike_eor", vis_filter=(0, 1, 'xx'))
np.all(sim.data.get_data(0, 0, 'xx') == 0)
```

```
[20]: True
```

```
[21]: np.all(sim.data.get_data(0, 1, 'xx') != 0) and np.all(sim.data.get_data(1, 0, 'xx') != 0)
```

```
[21]: True
```


Ordering of Effects

Some of the effects that can be simulated act on visibilities additively, whereas others act multiplicatively. The `Simulator` class keeps track of the order in which simulation components have been added, and issues warnings if the simulation components have been added out of order. In particular, it issues warnings if a multiplicative model is added to an empty set of visibilities or if an absolute visibility is added after a multiplicative effect has been added. Let's check it out.

```
[22]: # first, let's add a multiplicative effect
gains = sim.add("gains", seed_mode="once", ret_vis=True)
```

Note that you can set the `ret_vis` parameter to `True` in order to have the `add` method return the effect it calculated. In this case, it's a dictionary whose keys are antenna numbers and whose values are complex gains as a function of frequency.

```
[23]: # take a quick peek at the gains
fig = plt.figure(figsize=(11, 7))
ax = fig.add_subplot(111)
ax.plot(sim.freqs * 1e3, np.abs(gains[0]))
ax.set_xlabel("Frequency [MHz]", fontsize=12)
ax.set_ylabel("Gain Amplitude", fontsize=12)
plt.show()
```



Now let's try to add an additive effect, like EoR.

```
[24]: sim.add("noiselike_eor")
```

You are adding visibilities to a data array **after** multiplicative effects have been
→ introduced.

Voila! The Simulator knows that a multiplicative effect (bandpass gains) have already been applied to the data and issues a warning when an additive effect is added afterward. Now let's refresh the simulation and check what happens if we try to add gains immediately after.

```
[25]: sim.refresh()
```

```
[26]: # now try adding a multiplicative effect to a fresh simulation
gains = sim.add("gains", seed_mode="once", ret_vis=True)
```

You are trying to compute a multiplicative effect, but no visibilities have been
→ simulated yet.

```
[27]: # the effect is still simulated, but of course nothing happens
bool(gains) and np.all(sim.data.data_array == 0)
```

```
[27]: True
```

```
[28]: # note, however, that this warning is only issued once
sim.add("gains")
```

Using Custom Components

You can also use custom-defined callable objects as simulation components. Here's an example using a function:

```
[29]: # first, make up a function
def mock_vis(lsts, freqs):
    return np.ones((lst.size, freq.size), dtype=np.complex)

# then refresh the sim and add the effect
sim.refresh()
sim.add(mock_vis)

You are attempting to compute a component but have not specified an ``is_
multiplicative`` attribute for the component. The component will be added under the_
assumption that it is *not* multiplicative.
```

```
[30]: # and now let's see what it's logged as
print(sim.data.history)

hera_sim v1.0.0: Added mock_vis using kwargs:
```

```
[31]: # as for the components dictionary
sim._components

[31]: {<function __main__.mock_vis(lsts, freqs)>: {}}
```

Note that a warning is raised if a user-defined function (or callable class) does not have an `is_multiplicative` attribute—this will be the case for *all* functions, but class implementations can have such an attribute defined.

Registering Classes

To wrap this section up, let's briefly cover how the `Simulator` class knows what to look for when the `add` method is called. All of the simulation components defined in the `hera_sim` repo are designed as callable classes which inherit from a registry. A new registry can be created by defining a class and decorating it with the `registry` decorator:

```
[32]: from hera_sim import registry

@registry
class ExampleRegistry:
    is_multiplicative = False
    pass

class MockVis(ExampleRegistry):
    __aliases__ = ("mock_vis_alias",)
    def __call__(self, lsts, freqs):
        return np.ones((lst.size, freq.size), dtype=np.complex)
```

The above cell defines a new registry called `ExampleRegistry` and creates a class `MockVis` that is tracked by `ExampleRegistry`. Since the registry has its `is_multiplicative` attribute set to `False`, any class that inherits from it (and does not change the attribute's value) will also be considered an additive model.

```
[33]: ExampleRegistry._models
[33]: {'MockVis': __main__.MockVis}
```

```
[34]: MockVis.is_multiplicative
[34]: False
```

Since the `MockVis` class has "mock_vis_alias" as one of the entries in its `__aliases__` attribute, it can be discovered with that string:

```
[35]: sim.refresh()
sim.add("mock_vis_alias")
```

```
[36]: np.all(sim.data.data_array == 1)
[36]: True
```

```
[37]: print(sim.data.history)
hera_sim v1.0.0: Added MockVis using kwargs:
```

```
[38]: sim._components
[38]: {'mock_vis_alias': {}}
```

If you try to add a component that is not discoverable, then an exception will be raised and you'll be shown a list of known aliases:

```
[39]: # show the message this way to let the rest of the kernel run
try:
    sim.add("not_a_known_model")
except AttributeError as err:
    print(err)
```

The component 'not_a_known_model' wasn't found. The following aliases are known:
`cross_coupling_xtalk`, `thermal_noise`, `noiselikeeor`, `gen_gains`, `gen_reflection_gains`,
`impulse`, `gen_cross_coupling_xtalk`, `diffuseforeground`, `rfi_dtv`, `sigchain_reflections`,
`rfi_impulse`, `diffuse_foreground`, `gen_whitenoise_xtalk`, `white_noise_xtalk`, `dvt`,
`pointsourceforeground`, `hexarray`, `bandpass`, `gains`, `stations`, `rfi_stations`,
`lineararray`, `reflections`, `mockvis`, `thermalnoise`, `whitenoise_crosstalk`, `scatter`, `mock_vis_alias`, `crosscouplingcrosstalk`, `bandpass_gain`, `noiselike_eor`, `pntsrc_foreground`, `rfi_scatter`

If you would like to see what classes are registered and discoverable by the `Simulator` class, then you can use the `list_discoverable_components` function:

```
[40]: hera_sim.list_discoverable_components()

hera_sim.antpos.LinearArray
hera_sim.antpos.HexArray
hera_sim.foregrounds.DiffuseForeground
hera_sim.foregrounds.PointSourceForeground
hera_sim.noise.ThermalNoise
hera_sim.rfi.Stations
hera_sim.rfi.Impulse
hera_sim.rfi.Scatter
hera_sim.rfi.DTV
hera_sim.sigchain.Bandpass
hera_sim.sigchain.Reflections
hera_sim.sigchain.CrossCouplingCrosstalk
```

(continues on next page)

(continued from previous page)

```
hera_sim.sigchain.WhiteNoiseCrosstalk
hera_sim.eor.NoiselikeEoR
__main__.MockVis
```

One final caveat: currently, the `add` method is implemented so that an exception is raised when a user-defined function that does not exist in the global namespace is passed as the `component`. So, if you want to import a simulation component *that is implemented as a function* from some other module, then be sure to import the function into the global namespace.

The `run_sim` Method

The `Simulator` class also features the `run_sim` method, which allows you to run an entire simulation by either specifying a dictionary whose keys are strings that specify simulation components (or acceptable aliases) compatible with the `add` method and whose values are the optional parameter settings for the simulation components.

An Example

Let's keep the example short and sweet: diffuse foregrounds with bandpass gains.

```
[41]: # first, refresh the simulation to reset the history and _components
sim.refresh()

# now make a dictionary of simulation parameters
sim_params = {
    "diffuse_foreground" : {
        "Tsky_mdl" : Tsky_mdl, "omega_p" : omega_p, "seed_mode" : "redundantly"
    },
    "gains" : {"seed_mode" : "once"}
}

sim.run_sim(**sim_params)
```

```
[42]: # and let's inspect the history
print(sim.data.history)

hera_sim v1.0.0: Added DiffuseForeground using kwargs:
Tsky_mdl = <hera_sim.interpolators.Tsky object at 0x7fb870d28b50>
omega_p = <hera_sim.interpolators.Beam object at 0x7fb86dbd3390>
seed_mode = redundantly
hera_sim v1.0.0: Added Bandpass using kwargs:
seed_mode = once
```

We can also use a YAML file to control the simulation. Note the use of the YAML tags `!Tsky` and `!Beam`; these are defined in the `__yaml_constructors` module, and they use the `Tsky` and `Beam` classes, respectively, from the `interpolators` module to construct an interpolation object from the provided `datafile` (and optional `interp_kwargs` dictionary). Note that currently these classes assume that relative paths are intended to be relative to the `hera_sim.data` directory, but this behavior may change in the future.

```
[43]: # let's first make a configuration file
import tempfile
tempdir = tempfile.mkdtemp()
config = os.path.join(tempdir, "example.yaml")
```

(continues on next page)

(continued from previous page)

```

with open(config, 'w') as cfg:
    cfg.write(
"""
diffuse_foreground:
    Tsky_mdl: !Tsky
        datafile: HERA_Tsky_Reformatted.npz
    omega_p: !Beam
        datafile: HERA_H1C_BEAM_POLY.npy
    seed_mode: redundantly
gains:
    seed_mode: once
"""
)
# now refresh the simulation and run the new simulation
sim.refresh()
sim.run_sim(config)

```

```
[44]: # again let's look at the history
print(sim.data.history)

hera_sim v1.0.0: Added DiffuseForeground using kwargs:
Tsky_mdl = <hera_sim.interpolators.Tsky object at 0x7fb8704b5cd0>
omega_p = <hera_sim.interpolators.Beam object at 0x7fb86e8598d0>
seed_mode = redundantly
hera_sim v1.0.0: Added Bandpass using kwargs:
seed_mode = once
```

```
[45]: # and the components
sim._components

[45]: {'diffuse_foreground': {'Tsky_mdl': <hera_sim.interpolators.Tsky at 0x7fb8704b5cd0>,
                             'omega_p': <hera_sim.interpolators.Beam at 0x7fb86e8598d0>,
                             'seed_mode': 'redundantly'},
       'gains': {'seed_mode': 'once'}}
```

Finally, you can return individual components from a simulation like so:

```
[46]: # return some things, but not all things
sim_params["diffuse_foreground"]["ret_vis"] = True
sim_params["pntsrc_foreground"] = {"seed_mode": "redundantly", "ret_vis": True}

# reorder so that multiplicative effects come last
new_sim_params = {"diffuse_foreground": {}, "pntsrc_foreground": {}, "gains": {}}
new_sim_params.update(sim_params)

# refresh the simulation and run
sim.refresh()
results = dict(sim.run_sim(**new_sim_params))
```

```
[47]: # tada!
results.keys()

[47]: dict_keys(['diffuse_foreground', 'pntsrc_foreground'])
```

```
[48]: np.all(results['diffuse_foreground'].dtype == np.complex)
[48]: True

[49]: results['diffuse_foreground'].shape == sim.data.data_array.shape
[49]: True

[50]: np.all(
        np.isclose(results['diffuse_foreground'], sim.get("diffuse_foreground")))
)
[50]: True

[51]: sim.refresh()
sim.add("noiselike_eor", vis_filter=(0,1,'xx'))

[ ]:
```

The following tutorial will help you learn how to interface with the `defaults` module:

1.2.3 Guide for hera_sim Defaults and Simulator

This notebook is intended to be a guide for interfacing with the `hera_sim.defaults` module and using the `hera_sim.Simulator` class with the `run_sim` class method.

```
[1]: import os
import numpy as np
import matplotlib.pyplot as plt
import yaml

import uvtools
import hera_sim
from hera_sim import Simulator
from hera_sim.data import DATA_PATH
from hera_sim.config import CONFIG_PATH
%matplotlib inline

/home/bobby/HERA/dev/fix_tutorial/hera_sim/hera_sim/visibilities/__init__.py:27:_
→UserWarning: PRISim failed to import.
    warnings.warn("PRISim failed to import.")
/home/bobby/HERA/dev/fix_tutorial/hera_sim/hera_sim/visibilities/__init__.py:33:_
→UserWarning: VisGPU failed to import.
    warnings.warn("VisGPU failed to import.")
/home/bobby/HERA/dev/fix_tutorial/hera_sim/hera_sim/__init__.py:36: FutureWarning:
In the next major release, all HERA-specific variables will be removed from the_
→codebase. The following variables will need to be accessed through new class-like_
→structures to be introduced in the next major release:

noise.HERA_Tsky_mdl
noise.HERA_BEAM_POLY
sigchain.HERA_NRAO_BANDPASS
rfi.HERA_RFI_STATIONS

Additionally, the next major release will involve modifications to the package's API,_
→which move toward a regularization of the way in which hera_sim methods are_
→interfaced with; in particular, changes will be made such that the Simulator class_
→is the most intuitive way of interfacing with the hera_sim package features.
```

(continued from previous page)

FutureWarning)

We'll be using the `uvtools.plot.waterfall` function a few times throughout the notebook, but with a standardized way of generating plots. So let's write a wrapper to make these plots nicer:

```
[2]: # let's wrap it so that it'll work on Simulator objects
def waterfall(sim, antpairpol):
    """
    For reference, sim is a Simulator object, and antpairpol is a tuple with the
    form (ant1, ant2, pol).
    """
    freqs = np.unique(sim.data.freq_array) * 1e-9 # GHz
    lsts = np.unique(sim.data.lst_array) # radians
    vis = sim.data.get_data(antpairpol)

    # extent format is [left, right, bottom, top], vis shape is (NTIMES,NFREQS)
    extent = [freqs.min(), freqs.max(), lsts.max(), lsts.min()]

    fig = plt.figure(figsize=(12,8))
    axes = fig.subplots(2,1, sharex=True)
    axes[1].set_xlabel('Frequency [GHz]', fontsize=12)
    for ax in axes:
        ax.set_ylabel('LST [rad]', fontsize=12)

    fig.sca(axes[0])
    cax = uvtools.plot.waterfall(vis, mode='log', extent=extent)
    fig.colorbar(cax, label=r'$\log_{10}(V/Jy)$')

    fig.sca(axes[1])
    cax = uvtools.plot.waterfall(vis, mode='phs', extent=extent)
    fig.colorbar(cax, label='Phase [rad]')

    plt.tight_layout()
    plt.show()
```

```
[3]: # while we're preparing things, let's make a dictionary of default settings for
# creating a Simulator object

# choose a modest number of frequencies and times to simulate
NFREQ = 128
NTIMES = 32

# choose the channel width so that the bandwidth is 100 MHz
channel_width = 1e8 / NFREQ

# use just two antennas
ants = {0:(20.0,20.0,0), 1:(50.0,50.0,0)}

# use cross- and auto-correlation baselines
no_autos = False

# actually make the dictionary of initialization parameters
init_params = {'n_freq':NFREQ, 'n_times':NTIMES, 'antennas':ants,
               'channel_width':channel_width, 'no_autos':no_autos}
```

```
[4]: # turn off warnings; remove this cell in the future when this isn't a feature
hera_sim.defaults._warn = False
```

Defaults Basics

Let's first go over the basics of the `defaults` module. There are three methods that serve as the primary interface between the user and the `defaults` module: `set`, `activate`, and `deactivate`. These do what you'd expect them to do, but the `set` method requires a bit of extra work to interface with if you want to set custom default parameter values. We'll cover this later; for now, we'll see how you can switch between defaults characteristic to different observing seasons. Currently, we support default settings for the H1C observing season and the H2C observing season, and these may be accessed using the strings '`'h1c'`' and '`'h2c'`', respectively.

```
[5]: # first, let's note that the defaults are initially deactivated
hera_sim.defaults._override_defaults
```

```
[5]: False
```

```
[6]: # so let's activate the season defaults
hera_sim.defaults.activate()
hera_sim.defaults._override_defaults
```

```
[6]: True
```

```
[7]: # now that the defaults are activated, let's see what some differences are
```

```
# note that the defaults object is initialized with H1C defaults, but let's
# make sure that it's set to H1C defaults in case this cell is rerun later
hera_sim.defaults.set('h1c')
```

```
h1c_beam = hera_sim.noise._get_hera_bm_poly()
h1c_bandpass = hera_sim.sigchain._get_hera_bandpass()
```

```
# now change the defaults to the H2C observing season
hera_sim.defaults.set('h2c')
```

```
h2c_beam = hera_sim.noise._get_hera_bm_poly()
h2c_bandpass = hera_sim.sigchain._get_hera_bandpass()
```

```
# now compare them
print("H1C Defaults:\n \nBeam Polynomial: \n{}\nBandpass Polynomial: \n{}\n".
      format(h1c_beam, h1c_bandpass))
print("H2C Defaults:\n \nBeam Polynomial: \n{}\nBandpass Polynomial: \n{}\n".
      format(h2c_beam, h2c_bandpass))
```

```
H1C Defaults:
```

```
Beam Polynomial:
[ 8.07774113e+08 -1.02194430e+09  5.59397878e+08 -1.72970713e+08
 3.30317669e+07 -3.98798031e+06  2.97189690e+05 -1.24980700e+04
 2.27220000e+02]
```

```
Bandpass Polynomial:
[-2.04689451e+06  1.90683718e+06 -7.41348361e+05  1.53930807e+05
 -1.79976473e+04  1.12270390e+03 -2.91166102e+01]
```

```
H2C Defaults:
```

(continues on next page)

(continued from previous page)

```
Beam Polynomial:
[ 1.36744227e+13 -2.55445530e+13  2.14955504e+13 -1.07620674e+13
  3.56602626e+12 -8.22732117e+11  1.35321508e+11 -1.59624378e+10
  1.33794725e+09 -7.75754276e+07   2.94812713e+06 -6.58329699e+04
  6.52944619e+02]
Bandpass Polynomial:
[ 1.56076423e+17 -3.03924841e+17  2.72553042e+17 -1.49206626e+17
  5.56874144e+16 -1.49763003e+16  2.98853436e+15 -4.48609479e+14
  5.07747935e+13 -4.29965657e+12  2.67346077e+11 -1.18007726e+10
  3.48589690e+08 -6.15315646e+06  4.88747021e+04]
```

```
[8]: # another thing
fqs = np.linspace(0.1,0.2,1024)
lst = np.linspace(0,2*np.pi,100)

noise = hera_sim.noise.thermal_noise

hera_sim.defaults.set('h1c')
np.random.seed(0)
h1c_noise = noise(fqs,lst)

hera_sim.defaults.set('h2c')
np.random.seed(0)
h2c_noise = noise(fqs,lst)
np.random.seed(0)
still_h2c_noise = noise(fqs,lst)

# passing in a kwarg
np.random.seed(0)
other_noise = noise(fqs,lst,omega_p=np.ones(fqs.size))

# check things
print("H1C noise identical to H2C noise? {}".format(np.all(h1c_noise==h2c_noise)))
print("H2C noise identical to its other version? {}".format(np.all(h2c_noise==still_h2c_noise)))
print("Either noise identical to other noise? {}".format(np.all(h1c_noise==other_noise) or np.all(h2c_noise==other_noise)))

H1C noise identical to H2C noise? False
H2C noise identical to its other version? True
Either noise identical to other noise? False
```

```
[9]: # check out what the beam and bandpass look like
seasons = ('h1c', 'h2c')
beams = {'h1c': h1c_beam, 'h2c': h2c_beam}
bps = {'h1c': h1c_bandpass, 'h2c': h2c_bandpass}
fig = plt.figure(figsize=(12,10))
axes = fig.subplots(2,2)
for j, ax in enumerate(axes[:,0]):
    seas = seasons[j]
    ax.set_xlabel('Frequency [MHz]', fontsize=12)
    ax.set_ylabel('Beam Size [sr]', fontsize=12)
    ax.set_title('HERA {} Beam Model'.format(seas.upper()), fontsize=12)
```


(continues on next page)

(continued from previous page)

```

    ax.plot(fqs * 1e3, np.polyval(beams[seas], fqs))
for j, ax in enumerate(axes[:,1]):
    seas = seasons[j]
    ax.set_xlabel('Frequency [MHz]', fontsize=12)
    ax.set_ylabel('Noiseless Bandpass Gain', fontsize=12)
    ax.set_title('HERA {} Bandpass Model'.format(seas.upper()), fontsize=12)
    ax.plot(fqs * 1e3, np.polyval(bps[seas], fqs))
plt.tight_layout()
plt.show()

```



```

[10]: # let's look at the configuration that's initially loaded in
hera_sim.defaults._raw_config
[10]: {'foregrounds': {'diffuse_foreground': {'Tsky_mdl': <hera_sim.interpolators.Tsky at
    ↪0x7f52e274cd90>,
    'omega_p': <hera_sim.interpolators.Beam at 0x7f52e27561d0>},
    'io': {'empty_uvdata': {'start_freq': 46920776.3671875,
    'channel_width': 122070.3125,
    'integration_time': 8.59}},
    'noise': {'_get_hera_bm_poly': {'bm_poly': 'HERA_H2C_BEAM_POLY.npy'},
    'resample_Tsky': {'Tsky': 180.0, 'mfreq': 0.18, 'index': -2.5},

```

(continues on next page)

(continued from previous page)

```
'sky_noise_jy': {'inttime': 8.59},
'thermal_noise': {'Tsky_mdl': <hera_sim.interpolators.Tsky at 0x7f52e275e810>,
'omega_p': <hera_sim.interpolators.Beam at 0x7f52e275eb10>,
'Trx': 0,
'inttime': 8.59}},
'rfi': {'_get_hera_stations': {'rfi_stations': 'HERA_H2C_RFI_STATIONS.npy'},
'rfi_impulse': {'chance': 0.001, 'strength': 20.0},
'rfi_scatter': {'chance': 0.0001, 'strength': 10.0, 'std': 10.0},
'rfi_dtv': {'freq_min': 0.174,
'freq_max': 0.214,
'width': 0.008,
'chance': 0.0001,
'strength': 10.0,
'strength_std': 10.0}},
'sigchain': {'_get_hera_bandpass': {'bandpass': 'HERA_H2C_BANDPASS.npy'},
'gen_bandpass': {'gain_spread': 0.1},
'gen_whitenoise_xtalk': {'amplitude': 3.0},
'gen_cross_coupling_xtalk': {'amp': 0.0, 'dly': 0.0, 'phs': 0.0}}}
```

[11]: # and what about the set of defaults actually used?

```
hera_sim.defaults._config
```

[11]:

```
{'Tsky_mdl': <hera_sim.interpolators.Tsky at 0x7f52e275e810>,
'omega_p': <hera_sim.interpolators.Beam at 0x7f52e275eb10>,
'start_freq': 46920776.3671875,
'channel_width': 122070.3125,
'integration_time': 8.59,
'bm_poly': 'HERA_H2C_BEAM_POLY.npy',
'Tsky': 180.0,
'mfreq': 0.18,
'index': -2.5,
'inttime': 8.59,
'Trx': 0,
'rfi_stations': 'HERA_H2C_RFI_STATIONS.npy',
'chance': 0.0001,
'strength': 10.0,
'std': 10.0,
'freq_min': 0.174,
'freq_max': 0.214,
'width': 0.008,
'strength_std': 10.0,
'bandpass': 'HERA_H2C_BANDPASS.npy',
'gain_spread': 0.1,
'amplitude': 3.0,
'amp': 0.0,
'dly': 0.0,
'phs': 0.0}
```

[12]: # let's make two simulator objects

```
sim1 = Simulator(**init_params)
```

```
sim2 = Simulator(**init_params)
```

[13]: # parameters for two different simulations

```
hera_sim.defaults.set('h1c')
sim1params = {'pntsrc_foreground': {},
'noiselike_eor': {}},
```

(continues on next page)


(continued from previous page)

```


        'diffuse_foreground': {}
hera_sim.defaults.set('h2c')
sim2params = {'pntsrc_foreground': {},
              'noiselike_eor': {},
              'diffuse_foreground': {}}
sim1.run_sim(**sim1params)
sim2.run_sim(**sim2params)

```

[14]: `antpairpol = (0,1,'xx')`
`waterfall(sim1, antpairpol)`



[15]: `waterfall(sim2, antpairpol)`



[]:

The following tutorial will give you an overview of how to use `hera_sim` from the command line:

1.2.4 Running `hera_sim` from the command line

As of v0.2.0 of `hera_sim`, quick-and-dirty simulations can be run from the command line by creating a configuration file and using `hera_sim`'s `run` command to create simulated data in line with the configuration's specifications. The basic syntax of using `hera_sim`'s command-line interface is:

```
$ hera_sim run --help
bash: line 1: hera_sim: command not found
```

An example configuration file can be found in the `config_examples` directory of the repo's top-level directory. Here are its contents:

```
$ cat -n ../config_examples/template_config.yaml
 1      # This document is intended to serve as a template for constructing new
 2      # configuration YAMLs for use with the command-line interface.
 3
 4      bda:
 5          max_decorr: 0
 6          pre_fs_int_time: !dimensionful
 7              value: 0.1
```

(continues on next page)

(continued from previous page)

```

8         units: 's'
9         corr_FoV_angle: !dimensionful
10        value: 20
11        units: 'deg'
12        max_time: !dimensionful
13        value: 16
14        units: 's'
15        corr_int_time: !dimensionful
16        value: 2
17        units: 's'
18        filing:
19        outdir: '.'
20        outfile_name: 'quick_and_dirty_sim.uvh5'
21        output_format: 'uvh5'
22        clobber: True
23        # freq and time entries currently configured for hera_sim use
24        freq:
25        n_freq: 100
26        channel_width: 122070.3125
27        start_freq: 46920776.3671875
28        time:
29        n_times: 10
30        integration_time: 8.59
31        start_time: 2457458.1738949567
32        telescope:
33        # generate from an antenna layout csv
34        # array_layout: 'antenna_layout.csv'
35        # generate using hera_sim.antpos
36        array_layout: !antpos
37        array_type: "hex"
38        hex_num: 3
39        sep: 14.6
40        split_core: False
41        outriggers: 0
42        omega_p: !Beam
43        # non-absolute paths are assumed to be specified relative to the
44        # hera_sim data path
45        datafile: HERA_H2C_BEAM_MODEL.npz
46        interp_kwarg:
47        interpolator: interp1d
48        fill_value: extrapolate
49        # if you want to use a polynomial interpolator instead, then
50        # interpolator: poly1d
51        # kwargs not accepted for this; see numpy.poly1d_
52        documentation
53        defaults:
54        # This must be a string specifying an absolute path to a default
55        # configuration file or one of the season default keywords
56        'h2c'
57        systematics:
58        rfi:
59        # see hera_sim.rfi documentation for details on parameter names
60        rfi_stations:
61        seed: once
62        stations: !!null
63        rfi_impulse:
64        impulse_chance: 0.001

```

(continues on next page)

(continued from previous page)

```

64          impulse_strength: 20.0
65      rfi_scatter:
66          scatter_chance: 0.0001
67          scatter_strength: 10.0
68          scatter_std: 10.0
69      rfi_dtv:
70          seed: once
71          dtv_band:
72              - 0.174
73              - 0.214
74          dtv_channel_width: 0.008
75          dtv_chance: 0.0001
76          dtv_strength: 10.0
77          dtv_std: 10.0
78      sigchain:
79          gains:
80              seed: once
81              gain_spread: 0.1
82              dly_rng: [-20, 20]
83              bp_poly: HERA_H1C_BANDPASS.npy
84      sigchain_reflections:
85          seed: once
86          amp: !!null
87          dly: !!null
88          phs: !!null
89  crosstalk:
90      # only one of the two crosstalk methods should be specified
91  gen_whitenoise_xtalk:
92      amplitude: 3.0
93  # gen_cross_coupling_xtalk:
94      # seed: initial
95      # amp: !!null
96      # dly: !!null
97      # phs: !!null
98  noise:
99      thermal_noise:
100         seed: initial
101         Trx: 0
102 sky:
103     Tsky_mdl: !Tsky
104     # non-absolute paths are assumed to be relative to the hera_sim
105     # data folder
106     datafile: HERA_Tsky_Reformatted.npz
107     # interp kwargs are passed to scipy.interp.RectBivariateSpline
108     interp_kwargs:
109         pol: xx # this is popped when making a Tsky object
110 eor:
111     noiselike_eor:
112         eor_amp: 0.00001
113         min_delay: !!null
114         max_delay: !!null
115         seed: redundant # so redundant baselines see same sky
116         fringe_filter_type: tophat
117 foregrounds:
118     # if using hera_sim.foregrounds
119     diffuse_foreground:
120         seed: redundant # redundant baselines see same sky

```

(continues on next page)

(continued from previous page)

```

121         delay_filter_kwarg:
122             standoff: 0
123             delay_filter_type: tophat
124             normalize: !null
125         fringe_filter_kwarg:
126             fringe_filter_type: tophat
127     pntsrc_foreground:
128         seed: once
129         nsrcts: 1000
130         Smin: 0.3
131         Smax: 300
132         beta: -1.5
133         spectral_index_mean: -1.0
134         spectral_index_std: 0.5
135         reference_freq: 0.5
136         # Note regarding seed_redundantly:
137         # This ensures that baselines within a redundant group see the same sky;
138         # however, this does not ensure that the sky is actually consistent. So,
139         # while the data produced can be absolutely calibrated, it cannot be
140         # used to make sensible images (at least, I don't *think* it can be).
141
142     simulation:
143         # specify which components to simulate in desired order
144         # this should be a complete list of the things to include if hera_sim
145         # is the simulator being used. this will necessarily look different
146         # if other simulators are used, but that's not implemented yet
147         #
148         components: [foregrounds,
149             noise,
150             eor,
151             rfi,
152             sigchain, ]
153         # list particular model components to exclude from simulation
154         exclude: [sigchain_reflections,
155             gen_whitenoise_xtalk, ]

```

The remainder of this tutorial will be spent on exploring each of the items in the above configuration file.

BDA

The following block of text shows all of the options that must be specified if you would like to apply BDA to the simulated data. Note that BDA is applied at the very end of the script, and requires the BDA package to be installed from http://github.com/HERA-Team/baseline_dependent_averaging.

```
$ sed -n 4,17p ./config_examples/template_config.yaml
bda:
    max_decorr: 0
    pre_fs_int_time: !dimensionful
        value: 0.1
        units: 's'
```

(continues on next page)

(continued from previous page)

```

corr_FoV_angle: !dimensionful
    value: 20
    units: 'deg'
max_time: !dimensionful
    value: 16
    units: 's'
corr_int_time: !dimensionful
    value: 2
    units: 's'

```

Please refer to the `bda.apply_bda` documentation for details on what each parameter represents. Note that practically each entry has the tag `!dimensionful`; this YAML tag converts the entries in `value` and `units` to an `astropy.units.quantity.Quantity` object with the specified value and units.

Filing

The following block of text shows all of the options that may be specified in the `filng` section; however, not all of these *must* be specified. In fact, the only parameter that is required to be specified in the config YAML is `output_format`, and it must be either `miriad`, `uvfits`, or `uvh5`. These are currently the only supported write methods for `UVData` objects.

```

$ sed -n 18,24p ../config_examples/template_config.yaml
filng:
    outdir: '.'
    outfile_name: 'quick_and_dirty_sim.uvh5'
    output_format: 'uvh5'
    clobber: True
# freq and time entries currently configured for hera_sim use
freq:

```

Recall that `run` can be called with the option `--outfile`; this specifies the full path to where the simulated data should be saved and overrides the `outdir` and `outfile_name` settings from the config YAML. Additionally, one can choose to use the flag `-c` or `--clobber` in place of specifying `clobber` in the config YAML. Finally, the dictionary defined by the `kwargs` entry has its contents passed to whichever write method is chosen, and the `save_seeds` option should only be used if the `seed_redundantly` option is specified for any of the simulation components.

Setup

The following block of text contains three sections: `freq`, `time`, and `telescope`. These sections are used to initialize the `Simulator` object that is used to perform the simulation. Note that the config YAML shows all of the options that may be specified, but not all options are necessarily required.

```

$ sed -n 26,53p ../config_examples/template_config.yaml
    channel_width: 122070.3125
    start_freq: 46920776.3671875
time:
    n_times: 10
    integration_time: 8.59
    start_time: 2457458.1738949567
telescope:
    # generate from an antenna layout csv
    # array_layout: 'antenna_layout.csv'

```

(continues on next page)

(continued from previous page)

```
# generate using hera_sim.antpos
array_layout: !antpos
    array_type: "hex"
    hex_num: 3
    sep: 14.6
    split_core: False
    outriggers: 0
omega_p: !Beam
    # non-absolute paths are assumed to be specified relative to the
    # hera_sim data path
    datafile: HERA_H2C_BEAM_MODEL.npz
    interp_kwargs:
        interpolator: interp1d
        fill_value: extrapolate
        # if you want to use a polynomial interpolator instead, then
        # interpolator: poly1d
        # kwargs not accepted for this; see numpy.poly1d documentation
defaults:
    # This must be a string specifying an absolute path to a default
```

If you are familiar with using configuration files with pyuvsim, then you'll notice that the sections shown above look very similar to the way config files are constructed for use with pyuvsim. The config files for `run` were designed as an extension of the `pyuvsim` config files, with the caveat that some of the naming conventions used in `pyuvsim` are somewhat different than those used in `hera_sim`. For information on the parameters listed in the `freq` and `time` sections, please refer to the documentation for `hera_sim.io.empty_uvdata`. As for the `telescope` section, this is where the antenna array and primary beam are defined. The `array_layout` entry specifies the array, either by specifying an antenna layout file or by using the `!antpos` YAML tag and specifying the type of array (currently only `linear` and `hex` are supported) and the parameters to be passed to the corresponding function in `hera_sim.antpos`. The `omega_p` entry is where the primary beam is specified, and it is currently assumed that the beam is the same for each simulation component (indeed, this simulator is not intended to produce super-realistic simulations, but rather perform simulations quickly and give somewhat realistic results). This entry defines an interpolation object to be used for various `hera_sim` functions which require such an object; please refer to the documentation for `hera_sim.interpolators.Beam` for more information. Future versions of `hera_sim` will provide support for specifying the beam in an antenna layout file, similar to how it is done by `pyuvsim`.

Defaults

This section of the configuration file is optional to include. This section gives the user the option to use a default configuration to specify different parameters throughout the codebase. Users may define their own default configuration files, or they may use one of the provided season default configurations, located in the `config` folder. The currently supported season configurations are `h1c` and `h2c`. Please see the `defaults` module/documentation for more information.

```
$ sed -n 54,57p ../config_examples/template_config.yaml
    # configuration file or one of the season default keywords
    'h2c'
systematics:
    rfi:
```

Systematics

This is the section where any desired systematic effects can be specified. The block of text shown below details all of the possible options for systematic effects. Note that currently the `sigchain_reflections` and `gen_cross_coupling_xtalk` sections cannot easily be worked with; in fact, `gen_cross_coupling_xtalk` does not work as intended (each baseline has crosstalk show up at the same phase and delay, with the same amplitude, but uses a different autocorrelation visibility). Also note that the `rfi` section is subject to change, pending a rework of the `rfi` module.

```
$ sed -n 58,96p ./config_examples/template_config.yaml
# see hera_sim.rfi documentation for details on parameter names
rfi_stations:
    seed: once
    stations: !!null
rfi_impulse:
    impulse_chance: 0.001
    impulse_strength: 20.0
rfi_scatter:
    scatter_chance: 0.0001
    scatter_strength: 10.0
    scatter_std: 10.0
rfi_dtv:
    seed: once
    dtv_band:
        - 0.174
        - 0.214
    dtv_channel_width: 0.008
    dtv_chance: 0.0001
    dtv_strength: 10.0
    dtv_std: 10.0
sigchain:
    gains:
        seed: once
        gain_spread: 0.1
        dly_rng: [-20, 20]
        bp_poly: HERA_H1C_BANDPASS.npy
    sigchain_reflections:
        seed: once
        amp: !!null
        dly: !!null
        phs: !!null
crosstalk:
    # only one of the two crosstalk methods should be specified
    gen_whitenoise_xtalk:
        amplitude: 3.0
    # gen_cross_coupling_xtalk:
        # seed: initial
        # amp: !!null
        # dly: !!null
```

Note that although these simulation components are listed under `systematics`, they do not necessarily need to be listed here; the configuration file is formatted as such just for semantic clarity. For information on any particular simulation component listed here, please refer to the corresponding function's documentation. For those who may not know what it means, `!!null` is how `NoneType` objects are specified using `pyyaml`.

Sky

This section specifies both the sky temperature model to be used throughout the simulation as well as any simulation components which are best interpreted as being associated with the sky (rather than as a systematic effect). Just like the `systematics` section, these do not necessarily need to exist in the `sky` section (however, the `Tsky_mdl` entry *must* be placed in this section, as that's where the script looks for it).

```
$ sed -n 97,130p ../config_examples/template_config.yaml
      # phs: !!null
noise:
    thermal_noise:
        seed: initial
        Trx: 0
sky:
    Tsky_mdl: !Tsky
        # non-absolute paths are assumed to be relative to the hera_sim
        # data folder
        datafile: HERA_Tsky_Reformatted.npz
        # interp kwargs are passed to scipy.interpolate.RectBivariateSpline
        interp_kwargs:
            pol: xx # this is popped when making a Tsky object
eor:
    noiselike_eor:
        eor_amp: 0.00001
        min_delay: !!null
        max_delay: !!null
        seed: redundant # so redundant baselines see same sky
        fringe_filter_type: tophat
foregrounds:
    # if using hera_sim.foregrounds
    diffuse_foreground:
        seed: redundant # redundant baselines see same sky
        delay_filter_kwargs:
            standoff: 0
            delay_filter_type: tophat
            normalize: !!null
        fringe_filter_kwargs:
            fringe_filter_type: tophat
    pntsrc_foreground:
        seed: once
        nsrcts: 1000
        Smin: 0.3
```

As of now, `run` only supports simulating effects using the functions in `hera_sim`; however, we intend to provide support for using different simulators in the future. If you would like more information regarding the `Tsky_mdl` entry, please refer to the documentation for the `hera_sim.interpolators.Tsky` class. Finally, note that the `seed_redundantly` parameter is specified for each entry in `eor` and `foregrounds`; this parameter is used to ensure that baselines within a redundant group all measure the same visibility, which is a necessary feature for data to be absolutely calibrated. Please refer to the documentation for `hera_sim.eor` and `hera_sim.foregrounds` for more information on the parameters and functions listed above.

Simulation

This section is used to specify which of the simulation components to include in or exclude from the simulation. There are only two entries in this section: `components` and `exclude`. The `components` entry should be a list specifying which of the groups from the `sky` and `systematics` sections should be included in the simulation. The `exclude` entry should be a list specifying which of the particular models should not be simulated. Here's an example:

```
$ sed -n -e 137,138p -e 143,150p ./config_examples/template_config.yaml
    # This ensures that baselines within a redundant group see the same sky;
    # however, this does not ensure that the sky is actually consistent. So,
# specify which components to simulate in desired order
# this should be a complete list of the things to include if hera_sim
# is the simulator being used. this will necessarily look different
# if other simulators are used, but that's not implemented yet
#
components: [foregrounds,
              noise,
              eor,
```

The entries listed above would result in a simulation that includes all models contained in the `foregrounds`, `noise`, `eor`, `rfi`, and `sigchain` dictionaries, except for the `sigchain_reflections` and `gen_whitenoise_xtalk` models. So the simulation would consist of diffuse and point source foregrounds, thermal noise, noiselike EoR, all types of RFI modeled by `hera_sim`, and bandpass gains, with the effects simulated in that order. It is important to make sure that effects which enter multiplicatively (i.e. models from `sigchain`) are simulated *after* effects that enter additively, since the order that the simulation components are listed in is the same as the order of execution.

1.3 API Reference

1.3.1 Modules

`hera_sim.vis`

<code>hera_sim.antpos</code>	A module for creating antenna array configurations.
<code>hera_sim.defaults</code>	Class for dynamically changing <code>hera_sim</code> parameter defaults.
<code>hera_sim.eor</code>	A module for simulating EoR-like visibilities.
<code>hera_sim.foregrounds</code>	Reimagining of the foregrounds module, using an object-oriented approach.
<code>hera_sim.interpolators</code>	This module provides interfaces to different interpolation classes.

`hera_sim.io`

<code>hera_sim.noise</code>	Make some noise.
<code>hera_sim.rfi</code>	v1 implementation of RFI.
<code>hera_sim.sigchain</code>	Object-oriented approach to signal chain systematics.
<code>hera_sim.simulate</code>	Re-imagining of the simulation module.
<code>hera_sim.utils</code>	Utility module

hera_sim.vis

Functions

<code>sim_red_data(reds[, gains, shape, gain_scatter])</code>	Simulate thermal-noise-free random but redundant (up to differing gains) visibilities.
---	--

hera_sim.vis.sim_red_data

`hera_sim.vis.sim_red_data(reds, gains=None, shape=(10, 10), gain_scatter=0.1)`
Simulate thermal-noise-free random but redundant (up to differing gains) visibilities.

Parameters

- **reds** (*list of list of tuples*) – list of lists of baseline-pol tuples where each sublist has only redundant pairs
- **gains** (*dict*) – pre-specify base gains to then scatter on top of in the `{(index,antpol): ndarray}` format. Default gives all ones.
- **shape** (*tuple*) – (Ntimes, Nfreqs).
- **gain_scatter** (*float*) – relative amplitude of per-antenna complex gain scatter

Returns *dict* – true gains used in the simulation in the `{(index,antpol): np.array}` format
dict: true underlying visibilities in the `{(ind1,ind2,pol): np.array}` format
dict: simulated visibilities in the `{(ind1,ind2,pol): np.array}` format

hera_sim.antpos

A module for creating antenna array configurations.

Input parameters vary between functions, but all functions return a dictionary whose keys refer to antenna numbers and whose values refer to the ENU position of the antennas.

Classes

<code>HexArray([sep, split_core, outriggers])</code>	Build a hexagonal array configuration, nominally matching HERA.
<code>LinearArray([sep])</code>	Build a linear (east-west) array configuration.

hera_sim.antpos.HexArray

```
class hera_sim.antpos.HexArray(sep=14.6, split_core=True, outriggers=2)
    Build a hexagonal array configuration, nominally matching HERA.
```

Methods

```
__init__([sep, split_core, outriggers])
```

Parameters

- **sep** (*int, optional*) – The separation between adjacent grid points, in meters.

hera_sim.antpos.HexArray.__init__

```
HexArray.__init__(sep=14.6, split_core=True, outriggers=2)
```

Parameters

- **sep** (*int, optional*) – The separation between adjacent grid points, in meters. Default separation is 14.6 meters.
- **split_core** (*bool, optional*) – Whether to fracture the core into tridents that subdivide a hexagonal grid. Loses N antennas. Default behavior is to split the core.
- **outriggers** (*int, optional*) – The number of rings of outriggers to add to the array. The outriggers tile with the core to produce a fully-sampled UV plane. The first ring corresponds to the exterior of a hex_num=3 hexagon. For R outriggers, $3R^2 + 9R$ antennas are added to the array.

Attributes

```
is_multiplicative
```

hera_sim.antpos.HexArray.is_multiplicative

```
HexArray.is_multiplicative = False
```

hera_sim.antpos.LinearArray

```
class hera_sim.antpos.LinearArray(sep=14.6)
    Build a linear (east-west) array configuration.
```

Methods

```
__init__([sep])
```

Parameters `sep` (*float, optional*) – The separation between adjacent antennas, in meters.

hera_sim.antpos.LinearArray.__init__

```
LinearArray.__init__(sep=14.6)
```

Parameters `sep` (*float, optional*) – The separation between adjacent antennas, in meters. Default separation is 14.6 meters.

Attributes

```
is_multiplicative
```

hera_sim.antpos.LinearArray.is_multiplicative

```
LinearArray.is_multiplicative = False
```

hera_sim.defaults

This module is designed to allow for easy interfacing with simulation default parameters in an interactive environment.

hera_sim.eor

A module for simulating EoR-like visibilities.

EoR models should require lsts, frequencies, and a baseline vector as arguments, and may have arbitrary optional parameters. Models should return complex-valued arrays with shape (Nlst, Nfreqs) that represent a visibility appropriate for the given baseline.

Classes

`NoiselikeEoR([eor_amp, min_delay, ...])` Generate a noiselike, fringe-filtered EoR visibility.

hera_sim.eor.NoiselikeEoR

class `hera_sim.eor.NoiselikeEoR(eor_amp=1e-05, min_delay=None, max_delay=None, fringe_filter_type='tophat',fringe_filter_kwarg={})`
Generate a noiselike, fringe-filtered EoR visibility.

Parameters `eor_amp (float)`

Methods

`__init__([eor_amp, min_delay, max_delay, ...])`

hera_sim.eor.NoiselikeEoR.__init__

`NoiselikeEoR.__init__(eor_amp=1e-05, min_delay=None, max_delay=None, fringe_filter_type='tophat',fringe_filter_kwarg={})`

Attributes

`is_multiplicative`

hera_sim.eor.NoiselikeEoR.is_multiplicative

`NoiselikeEoR.is_multiplicative = False`

hera_sim.foregrounds

Reimagining of the foregrounds module, using an object-oriented approach.

Classes

`DiffuseForeground([Tsky_mdl, omega_p, ...])`

`PointSourceForeground([nsrcs, Smin, Smax, ...])`

hera_sim.foregrounds.DiffuseForeground

```
class hera_sim.foregrounds.DiffuseForeground(Tsky_mdl=None, omega_p=None,
                                              delay_filter_kwarg=None,
                                              fringe_filter_kwarg=None)
```

Methods

```
__init__([Tsky_mdl, omega_p, ...])
```

Parameters

- **Tsky_mdl** (*interpolation object*)
– Sky temperature model, in units of Kelvin. Must be callable

hera_sim.foregrounds.DiffuseForeground.__init__

```
DiffuseForeground.__init__(Tsky_mdl=None, omega_p=None, delay_filter_kwarg=None,
                           fringe_filter_kwarg=None)
```

Parameters

- **Tsky_mdl** (*interpolation object*) – Sky temperature model, in units of Kelvin. Must be callable with signature Tsky_mdl(lsts, freqs), formatted so that lsts are in radians and freqs are in GHz.
- **omega_p** (*interpolation object or array-like of float*) – Beam size model, in units of steradian. If passing an array, then it must be the same shape as the frequency array passed to the freqs parameter.
- **delay_filter_kwarg** (*dict, optional*) – Keyword arguments and associated values to be passed to .. func:: utils.rough_delay_filter. Default is to use the following settings:
standoff : 0.0 delay_filter_type : tophat
- **fringe_filter_kwarg** (*dict, optional*) – Keyword arguments and associated values to be passed to .. func:: utils.rough_fringe_filter. Default is to use the following settings:
fringe_filter_type : tophat

Attributes

```
is_multiplicative
```

hera_sim.foregrounds.DiffuseForeground.is_multiplicative

```
DiffuseForeground.is_multiplicative = False
```

hera_sim.foregrounds.PointSourceForeground

```
class hera_sim.foregrounds.PointSourceForeground(nsrs=1000, Smin=0.3, Smax=300,
                                                beta=-1.5, spectral_index_mean=-1,
                                                spectral_index_std=0.5, reference_freq=0.15)
```

Methods

`__init__([nsrs, Smin, Smax, beta, ...])`

Parameters

- **nsrs** (*int, optional*) – Number of sources to place on the sky. Point sources are

hera_sim.foregrounds.PointSourceForeground.__init__

```
PointSourceForeground.__init__(nsrs=1000, Smin=0.3, Smax=300, beta=-1.5,
                             spectral_index_mean=-1, spectral_index_std=0.5,
                             reference_freq=0.15)
```

Parameters

- **nsrs** (*int, optional*) – Number of sources to place on the sky. Point sources are simulated to have a flux-density drawn from a power-law distribution specified by the `Smin`, `Smax`, and `beta` parameters. Additionally, each source has a chromatic flux-density given by a power law; the spectral index is drawn from a normal distribution with mean `spectral_index_mean` and standard deviation `spectral_index_std`. The default behavior is to use 1000 sources.
- **Smin** (*float, optional*) – Lower bound of the power-law distribution to draw flux-densities from, in units of Jy. Default is 0.3 Jy.
- **Smax** (*float, optional*) – Upper bound of the power-law distribution to draw flux-densities from, in units of Jy. Default is 300 Jy.
- **beta** (*float, optional*) – Power law index for the source counts versus flux-density. Default is -1.5.
- **spectral_index_mean** (*float, optional*) – The mean of the normal distribution to draw source spectral indices from. Default is -1.
- **spectral_index_std** (*float, optional*) – The standard deviation of the normal distribution to draw source spectral indices from. Default is 0.5.
- **reference_freq** (*float, optional*) – Reference frequency used to make the point source flux densities chromatic, in units of GHz. Default is 0.15 GHz.

Attributes

`is_multiplicative`

`hera_sim.foregrounds.PointSourceForeground.is_multiplicative`

```
PointSourceForeground.is_multiplicative = False
```

hera_sim.interpolators

This module provides interfaces to different interpolation classes.

Classes

<code>Bandpass</code> (datafile, **interp_kwarg)	Bandpass interpolation object; subclass of <i>FreqInterpolator</i> .
<code>Beam</code> (datafile, **interp_kwarg)	Beam interpolation object; subclass of <i>FreqInterpolator</i> .
<code>FreqInterpolator</code> (datafile, **interp_kwarg)	Frequency interpolator; subclass of <i>Interpolator</i> .
<code>Interpolator</code> (datafile, **interp_kwarg)	Base interpolator class
<code>Tsky</code> (datafile, **interp_kwarg)	Sky temperature interpolator; subclass of <i>Interpolator</i> .

hera_sim.interpolators.Bandpass

```
class hera_sim.interpolators.Bandpass (datafile, **interp_kwarg)  
    Bandpass interpolation object; subclass of FreqInterpolator.
```

Methods

`__init__`(datafile, **interp_kwarg) Extend the *FreqInterpolator* constructor.

hera_sim.interpolators.Bandpass.__init__

```
Bandpass.__init__ (datafile, **interp_kwarg)  
    Extend the FreqInterpolator constructor.
```

Parameters

- **datafile** (*str*) – Passed to the superclass constructor.
- **interp_kwarg** (*unpacked dict, optional*) – Passed to the superclass constructor.

hera_sim.interpolators.Beam

class hera_sim.interpolators.Beam(datafile, **interp_kwarg)
Beam interpolation object; subclass of *FreqInterpolator*.

Methods

<u>__init__</u> (datafile, **interp_kwarg)	Extend the <i>FreqInterpolator</i> constructor.
--	---

hera_sim.interpolators.Beam.[__init__](#)

Beam.[__init__](#)(datafile, **interp_kwarg)
Extend the *FreqInterpolator* constructor.

Parameters

- **datafile** (*str*) – Passed to the superclass constructor.
- **interp_kwarg** (*unpacked dict, optional*) – Passed to the superclass constructor.

hera_sim.interpolators.FreqInterpolator

class hera_sim.interpolators.FreqInterpolator(datafile, **interp_kwarg)
Frequency interpolator; subclass of *Interpolator*.

Methods

<u>__init__</u> (datafile, **interp_kwarg)	Extend the <i>Interpolator</i> constructor.
--	---

hera_sim.interpolators.FreqInterpolator.[__init__](#)

FreqInterpolator.[__init__](#)(datafile, **interp_kwarg)
Extend the *Interpolator* constructor.

Parameters

- **datafile** (*str*) – Passed to the superclass constructor.
- **interp_kwarg** (*unpacked dict, optional*) – Extends superclass interp_kwarg parameter by checking for the key ‘interpolator’ in the dictionary. The ‘interpolator’ key should have the value ‘poly1d’ or ‘interp1d’; these correspond to the *np.poly1d* and *scipy.interpolate.interp1d* objects, respectively. If the ‘interpolator’ key is not found, then it is assumed that a *np.poly1d* object is to be used for the interpolator object.

Raises `AssertionError`: – This is raised if the choice of interpolator and the required type of the ref_file do not agree (i.e. trying to make a ‘poly1d’ object using a .npz file as a reference). An `AssertionError` is also raised if the .npz for generating an ‘interp1d’ object does not have the correct arrays in its archive.

hera_sim.interpolators.Interpolator

class hera_sim.interpolators.**Interpolator**(*datafile*, ***interp_kwarg*s)
Base interpolator class

Methods

<u>__init__</u> (<i>datafile</i> , ** <i>interp_kwarg</i> s)	Initialize an <i>Interpolator</i> object with necessary attributes.
---	---

hera_sim.interpolators.Interpolator.__init__

Interpolator.[__init__](#)(*datafile*, ***interp_kwarg*s)
Initialize an *Interpolator* object with necessary attributes.

Parameters

- **datafile** (*str*) – Path to the file to be used to generate the interpolation object. Must be either a .npy or .npz file, depending on which type of interpolation object is desired. If path is not absolute, then the file is assumed to exist in the *data* directory of *hera_sim* and is modified to reflect this assumption.
- **interp_kwarg**s (*unpacked dict, optional*) – Passed to the interpolation method used to make the interpolator.

hera_sim.interpolators.Tsky

class hera_sim.interpolators.**Tsky**(*datafile*, ***interp_kwarg*s)
Sky temperature interpolator; subclass of *Interpolator*.

Methods

<u>__init__</u> (<i>datafile</i> , ** <i>interp_kwarg</i> s)	Extend the <i>Interpolator</i> constructor.
---	---

hera_sim.interpolators.Tsky.__init__

Tsky.[__init__](#)(*datafile*, ***interp_kwarg*s)
Extend the *Interpolator* constructor.

Parameters

- **datafile** (*str*) – Passed to superclass constructor. Must be a .npz file with the following archives:
 - ‘**tsky**’: Array of sky temperature values in units of Kelvin; must have shape=(NPOLS, NLSTS, NFREQS).
 - ‘**freqs**’: Array of frequencies at which the tsky model is evaluated, in units of GHz; must have shape=(NFREQS,).

‘lsts’: Array of LSTs at which the tsky model is evaluated, in units of radians; must have shape=(NLSTS,).

‘meta’: Dictionary of metadata describing the data stored in the npz file. Currently it only needs to contain an entry ‘pols’, which lists the polarizations such that their order agrees with the ordering of arrays along the tsky axis-0. The user may choose to also save the units of the frequency, lst, and tsky arrays as strings in this dictionary.

- **interp_kwarg** (*unpacked dict, optional*) – Extend interp_kwarg parameter for superclass to allow for the specification of which polarization to use via the key ‘pol’. If ‘pol’ is specified, then it must be one of the polarizations listed in the ‘meta’ dictionary.

Variables

- **freqs** (*np.ndarray*) – Frequency array used to construct the interpolator object. Has units of GHz and shape=(NFREQS,).
- **lsts** (*np.ndarray*) – LST array used to construct the interpolator object. Has units of radians and shape=(NLSTS,).
- **tsky** (*np.ndarray*) – Sky temperature array used to construct the interpolator object. Has units of Kelvin and shape=(NPOLs, NLSTS, NFREQS).
- **meta** (*dict*) – Dictionary containing some metadata relevant to the interpolator.
- **pol** (*str, default ‘xx’*) – Polarization appropriate for the sky temperature model. Must be one of the polarizations stored in the ‘meta’ dictionary.

Raises Assertion`Error`: – Raised if any of the required npz keys are not found or if the tsky array does not have shape=(NPOLs, NLSTS, NFREQS).

Attributes

freqs

lsts

meta

tsky

hera_sim.interpolators.Tsky.freqs

property Tsky.freqs

hera_sim.interpolators.Tsky.lsts

property Tsky.lsts

hera_sim.interpolators.Tsky.meta

property Tsky.meta

hera_sim.interpolators.Tsky.tsky

property Tsky.tsky

hera_sim.io

Functions

<code>chunk_sim_and_save(sim_uvd, save_dir[, ...])</code>	Chunk the simulation data to match the reference file and write to disk.
<code>empty_uvdata([Ntimes, start_time, ...])</code>	

hera_sim.io.chunk_sim_and_save

hera_sim.io.**chunk_sim_and_save** (*sim_uvd*, *save_dir*, *ref_files=None*, *Nint_per_file=None*, *prefix=None*, *sky_cmp=None*, *state=None*, *filetype='uvh5'*, *clobber=True*)

Chunk the simulation data to match the reference file and write to disk.

Chunked files have the following naming convention: `save_dir/[{prefix}.]{jd_major}.{jd_minor}[.{sky_cmp}][.{state}].{filetype}`. The entries in brackets are optional and may be omitted.

Parameters

- **sim_uvd** (pyuvdata.UVData) – pyuvdata.UVData object containing the simulation data to chunk and write to disk.
- **save_dir** (*str or path-like object*) – Path to the directory where the chunked files will be saved.
- **ref_files** (*iterable of str*) – Iterable of filepaths to use for reference when chunking. This must be specified if *Nint_per_file* is not specified. This determines (and overrides, if also provided) *Nint_per_file* if provided.
- **Nint_per_file** (*int, optional*) – Number of integrations per chunked file. This must be specified if *ref_files* is not specified.
- **prefix** (*str, optional*) – Prefix of file basename. Default is to add no prefix.
- **sky_cmp** (*str, optional*) – String denoting which sky component has been simulated. Should be one of the following: ('foregrounds', 'eor', 'sum').
- **state** (*str, optional*) – String denoting whether the file is the true sky or corrupted.

- **filetype** (*str, optional*) – Format to use when writing files to disk. Must be a filetype supported by `pyuvdata.UVData`. Default is `uvh5`.
- **clobber** (*bool, optional*) – Whether to overwrite any existing files that share the new filenames. Default is to overwrite files.

hera_sim.io.empty_uvdata

```
hera_sim.io.empty_uvdata(Ntimes=None,      start_time=2456658.5,      integration_time=None,
                        array_layout=None,    Nfreqs=None,      start_freq=None,      chan-
                        nel_width=None,     n_freq=None,      n_times=None,      antennas=None,
                        conjugation=None, **kwargs)
```

hera_sim.noise

Make some noise.

Functions

```
resample_Tsky(lsts, freqs[, Tsky_mdl, Tsky, ...])
```

```
sky_noise_jy(lsts, freqs, **kwargs)
```

```
white_noise(*args, **kwargs)
```

hera_sim.noise.resample_Tsky

```
hera_sim.noise.resample_Tsky(lsts, freqs, Tsky_mdl=None, Tsky=180.0, mfreq=0.18, index=-2.5)
```

hera_sim.noise.sky_noise_jy

```
hera_sim.noise.sky_noise_jy(lsts, freqs, **kwargs)
```

hera_sim.noise.white_noise

```
hera_sim.noise.white_noise(*args, **kwargs)
```

Classes

ThermalNoise([Tsky_mdl, omega_p, ...])

hera_sim.noise.ThermalNoise

```
class hera_sim.noise.ThermalNoise(Tsky_mdl=None, omega_p=None, integration_time=None,  
channel_width=None, Trx=0, autovis=None)
```

Methods

__init__([Tsky_mdl, omega_p, ...])

resample_Tsky(lsts, freqs[, Tsky_mdl, Tsky,
...])

hera_sim.noise.ThermalNoise.__init__

```
ThermalNoise.__init__(Tsky_mdl=None, omega_p=None, integration_time=None, channel_width=None, Trx=0, autovis=None)
```

hera_sim.noise.ThermalNoise.resample_Tsky

```
static ThermalNoise.resample_Tsky(lsts, freqs, Tsky_mdl=None, Tsky=180.0, mfreq=0.18,  
index=-2.5)
```

Attributes

is_multiplicative

hera_sim.noise.ThermalNoise.is_multiplicative

```
ThermalNoise.is_multiplicative = False
```

hera_sim.rfi

v1 implementation of RFI. Consult w/ Steven for new RFI module.

Classes

```
DTV([dtv_band, dtv_channel_width, ...])
```

```
Impulse([impulse_chance, impulse_strength])
```

```
RfiStation(f0[, duty_cycle, strength, std, ...])
```

```
Scatter([scatter_chance, scatter_strength, ...])
```

```
Stations([stations])
```

hera_sim.rfi.DTV

```
class hera_sim.rfi.DTV(dtv_band=(0.174, 0.214), dtv_channel_width=0.008, dtv_chance=0.0001,  
                       dtv_strength=10.0, dtv_std=10.0)
```

Methods

```
__init__([dtv_band, dtv_channel_width, ...])
```

hera_sim.rfi.DTV.__init__

```
DTV.__init__(dtv_band=(0.174, 0.214), dtv_channel_width=0.008, dtv_chance=0.0001,  
            dtv_strength=10.0, dtv_std=10.0)
```

Attributes

```
is_multiplicative
```

hera_sim.rfi.DTV.is_multiplicative

```
DTV.is_multiplicative = False
```

hera_sim.rfi.Impulse

```
class hera_sim.rfi.Impulse(impulse_chance=0.001, impulse_strength=20.0)
```

Methods

```
__init__([impulse_chance, impulse_strength])
```

hera_sim.rfi.Impulse.__init__

```
Impulse.__init__(impulse_chance=0.001, impulse_strength=20.0)
```

Attributes

```
is_multiplicative
```

hera_sim.rfi.Impulse.is_multiplicative

```
Impulse.is_multiplicative = False
```

hera_sim.rfi.RfiStation

```
class hera_sim.rfi.RfiStation(f0, duty_cycle=1.0, strength=100.0, std=10.0, timescale=100.0)
```

Methods

```
__init__(f0[, duty_cycle, strength, std, ...]) Initialize self.
```

hera_sim.rfi.RfiStation.__init__

```
RfiStation.__init__(f0, duty_cycle=1.0, strength=100.0, std=10.0, timescale=100.0)  
    Initialize self. See help(type(self)) for accurate signature.
```

hera_sim.rfi.Scatter

```
class hera_sim.rfi.Scatter(scatter_chance=0.0001, scatter_strength=10.0, scatter_std=10.0)
```

Methods

```
__init__([scatter_chance, scatter_strength, ...])
```

hera_sim.rfi.Scatter.__init__

```
Scatter.__init__(scatter_chance=0.0001, scatter_strength=10.0, scatter_std=10.0)
```

Attributes

```
is_multiplicative
```

hera_sim.rfi.Scatter.is_multiplicative

```
Scatter.is_multiplicative = False
```

hera_sim.rfi.Stations

```
class hera_sim.rfi.Stations(stations=None)
```

Methods

```
__init__([stations])
```

hera_sim.rfi.Stations.__init__

Stations.**__init__**(stations=None)

Attributes

is_multiplicative

hera_sim.rfi.Stations.is_multiplicative

Stations.**is_multiplicative** = False

hera_sim.sigchain

Object-oriented approach to signal chain systematics.

Functions

apply_gains(vis, gains, bl)

gen_bandpass(freqs, ants[, gain_spread, bp_poly])

gen_delay_ph(freqs, ants[, dly_rng])

gen_reflection_coefficient(freqs, amp, dly,
phs)

vary_gains_in_time(gains, times[, freqs, ...]) Vary gain amplitudes, phases, or delays in time.

hera_sim.sigchain.apply_gains

hera_sim.sigchain.**apply_gains**(vis, gains, bl)

hera_sim.sigchain.gen_bandpass

```
hera_sim.sigchain.gen_bandpass (freqs, ants, gain_spread=0.1, bp_poly=None)
```

hera_sim.sigchain.gen_delay_ph

```
hera_sim.sigchain.gen_delay_ph (freqs, ants, dly_rng=(-20, 20))
```

hera_sim.sigchain.gen_reflection_coefficient

```
hera_sim.sigchain.gen_reflection_coefficient (freqs, amp, dly, phs, conj=False)
```

hera_sim.sigchain.vary_gains_in_time

```
hera_sim.sigchain.vary_gains_in_time (gains, times, freqs=None, delays=None, parameter='amp', variation_ref_time=None, variation_timescale=None, variation_amp=0.05, variation_mode='linear')
```

Vary gain amplitudes, phases, or delays in time.

If the gains initially have the form

$$g(\nu) = g_0(\nu) \exp(i2\pi\nu\tau + i\phi),$$

then the output gains have the form

$$g(\nu, t) = g_0(\nu, t) \exp(i2\pi\nu\tau(t) + i\phi(t)).$$

Parameters

- **gains** (*dict*) – Dictionary mapping antenna numbers to gain spectra/waterfalls.
- **times** (*array-like of float*) – Times at which to simulate time variation. Should be the same length as the data to which the gains will be applied. Should also be in the same units as `variation_ref_time` and `variation_timescale`.
- **freqs** (*array-like of float, optional*) – Frequencies at which the gains are evaluated, in GHz. Only needs to be specified for adding time variation to the delays.
- **delays** (*dict, optional*) – Dictionary mapping antenna numbers to gain delays, in ns.
- **parameter** (*str; optional*) – Which gain parameter to vary; must be one of (“amp”, “phs”, “dly”).
- **variation_ref_time** (*float or array-like of float, optional*) – Reference time(s) used for generating time variation. For linear and sinusoidal variation, this is the time where the gains are equal to their original, time-independent values. Should be in the same units as the `times` array. Default is to use the center of the `times` provided.
- **variation_timescale** (*float or array-like of float, optional*) – Timescale(s) for one cycle of the variation(s), in the same units as the provided `times`. Default is to use the duration of the entire `times` array.
- **variation_amp** (*float or array-like of float, optional*) – Amplitude(s) of the variation(s) introduced. This is *not* the peak-to-peak amplitude! This also does not have exactly the same interpretation for each type of variation mode. For amplitude and delay variation,

this represents the amplitude of modulations—so it can be interpreted as a fractional variation. For phase variation, this represents an absolute, time-dependent phase offset to introduce to the gains; however, it is still *not* a peak-to-peak amplitude.

- **variation_mode** (*str or array-like of str, optional*) – Which type(s) of variation to simulate. Supported modes are “linear”, “sinusoidal”, and “noiselike”. Default is “linear”. Note that the “linear” mode produces a triangle wave variation with period twice the corresponding timescale; this ensures that the gains vary linearly over the entire set of provided times if the default variation timescale is used.

Returns **time_varied_gains** (*dict*) – Dictionary mapping antenna numbers to gain waterfalls.

Classes

Bandpass([gain_spread, dly_rng, bp_poly])

CrossCouplingCrosstalk([amp, dly, phs, ...])

CrossCouplingSpectrum([Ncopies, amp_range, ...])

Reflections([amp, dly, phs, conj, ...])

WhiteNoiseCrosstalk([amplitude])

hera_sim.sigchain.Bandpass

class hera_sim.sigchain.**Bandpass** (*gain_spread=0.1, dly_rng=(- 20, 20), bp_poly=None*)

Methods

__init__([gain_spread, dly_rng, bp_poly])

hera_sim.sigchain.Bandpass.__init__

Bandpass.*__init__*(*gain_spread=0.1, dly_rng=(- 20, 20), bp_poly=None*)

Attributes

is_multiplicative

hera_sim.sigchain.Bandpass.is_multiplicative

```
Bandpass.is_multiplicative = True
```

hera_sim.sigchain.CrossCouplingCrosstalk

```
class hera_sim.sigchain.CrossCouplingCrosstalk(amp=None, dly=None, phs=None, conj=False, amp_jitter=0, dly_jitter=0)
```

Methods

```
__init__([amp, dly, phs, conj, amp_jitter, ...])
```

```
gen_reflection_coefficient(freqs, amp,  
dly, phs)
```

hera_sim.sigchain.CrossCouplingCrosstalk.__init__

```
CrossCouplingCrosstalk.__init__(amp=None, dly=None, phs=None, conj=False,  
amp_jitter=0, dly_jitter=0)
```

hera_sim.sigchain.CrossCouplingCrosstalk.gen_reflection_coefficient

```
static CrossCouplingCrosstalk.gen_reflection_coefficient(freqs, amp, dly,  
phs, conj=False)
```

Attributes

```
is_multiplicative
```

hera_sim.sigchain.CrossCouplingCrosstalk.is_multiplicative

```
CrossCouplingCrosstalk.is_multiplicative = False
```

hera_sim.sigchain.CrossCouplingSpectrum

```
class hera_sim.sigchain.CrossCouplingSpectrum(Ncopies=10, amp_range=(-4, -6), dly_range=(1000, 1200), phs_range=(-3.141592653589793, 3.141592653589793), amp_jitter=0, dly_jitter=0, symmetrize=True)
```

Methods

```
__init__([Ncopies, amp_range, dly_range, ...]) Initialize self.
```

hera_sim.sigchain.CrossCouplingSpectrum.__init__

```
CrossCouplingSpectrum.__init__(Ncopies=10, amp_range=(- 4, - 6), dly_range=(1000,  
1200), phs_range=(- 3.141592653589793,  
3.141592653589793), amp_jitter=0, dly_jitter=0,  
symmetrize=True)
```

Initialize self. See help(type(self)) for accurate signature.

Attributes

```
is_multiplicative
```

hera_sim.sigchain.CrossCouplingSpectrum.is_multiplicative

```
CrossCouplingSpectrum.is_multiplicative = False
```

hera_sim.sigchain.Reflections

```
class hera_sim.sigchain.Reflections(amp=None, dly=None, phs=None, conj=False,  
amp_jitter=0, dly_jitter=0)
```

Methods

```
__init__([amp, dly, phs, conj, amp_jitter, ...])
```

```
gen_reflection_coefficient(freqs, amp,  
dly, phs)
```

hera_sim.sigchain.Reflections.__init__

```
Reflections.__init__(amp=None, dly=None, phs=None, conj=False, amp_jitter=0,  
dly_jitter=0)
```

hera_sim.sigchain.Reflections.gen_reflection_coefficient

```
static Reflections.gen_reflection_coefficient(freqs, amp, dly, phs, conj=False)
```

Attributes

is_multiplicative

hera_sim.sigchain.Reflections.is_multiplicative

```
Reflections.is_multiplicative = True
```

hera_sim.sigchain.WhiteNoiseCrosstalk

```
class hera_sim.sigchain.WhiteNoiseCrosstalk(amplitude=3.0)
```

Methods

`__init__([amplitude])`

hera_sim.sigchain.WhiteNoiseCrosstalk.__init__

```
WhiteNoiseCrosstalk.__init__(amplitude=3.0)
```

Attributes

is_multiplicative

hera_sim.sigchain.WhiteNoiseCrosstalk.is_multiplicative

```
WhiteNoiseCrosstalk.is_multiplicative = False
```

hera_sim.simulate

Re-imagining of the simulation module.

Classes

<code>Simulator([data, defaults_config])</code>	Class for managing a simulation.
---	----------------------------------

hera_sim.simulate.Simulator

class `hera_sim.simulate.Simulator(data=None, defaults_config=None, **kwargs)`
Class for managing a simulation.

Methods

<code>__init__([data, defaults_config])</code>	Initialize a Simulator object.
<code>add(component, **kwargs)</code>	
<code>add_eor(model, **kwargs)</code>	Add an EoR-like model to the visibilities.
<code>add_foregrounds(model, **kwargs)</code>	Add foregrounds to the visibilities.
<code>add_gains(**kwargs)</code>	Apply bandpass gains to the visibilities.
<code>add_noise(model, **kwargs)</code>	Add thermal noise to the visibilities.
<code>add_rfi(model, **kwargs)</code>	Add RFI to the visibilities.
<code>add_sigchain_reflections([ants])</code>	Apply reflection gains to the visibilities.
<code>add_xtalk([model, bls])</code>	Add crosstalk to the visibilities.
<code>apply_defaults(config[, refresh])</code>	
<code>chunk_sim_and_save(save_dir[, ref_files, ...])</code>	Chunk a simulation in time and write to disk.
<code>get(component[, ant1, ant2, pol])</code>	
<code>plot_array()</code>	Generate a plot of the array layout in ENU coordinates.
<code>refresh()</code>	Refresh the Simulator object.
<code>run_sim([sim_file])</code>	
<code>write(filename[, save_format])</code>	

hera_sim.simulate.Simulator.__init__

`Simulator.__init__(data=None, defaults_config=None, **kwargs)`
Initialize a Simulator object.

Idea: Make Simulator object have three major components:

sim.data -> UVData object for storing the “measured” data Also keep track of most metadata here

sim.defaults -> Defaults object

hera_sim.simulate.Simulator.add

`Simulator.add(component, **kwargs)`

hera_sim.simulate.Simulator.add_eor

`Simulator.add_eor(model, **kwargs)`

Add an EoR-like model to the visibilities. See [add\(\)](#) for more details.

hera_sim.simulate.Simulator.add_foregrounds

`Simulator.add_foregrounds(model, **kwargs)`

Add foregrounds to the visibilities. See [add\(\)](#) for more details.

hera_sim.simulate.Simulator.add_gains

`Simulator.add_gains(**kwargs)`

Apply bandpass gains to the visibilities. See [add\(\)](#) for more details.

hera_sim.simulate.Simulator.add_noise

`Simulator.add_noise(model, **kwargs)`

Add thermal noise to the visibilities. See [add\(\)](#) for more details.

hera_sim.simulate.Simulator.add_rfi

`Simulator.add_rfi(model, **kwargs)`

Add RFI to the visibilities. See [add\(\)](#) for more details.

hera_sim.simulate.Simulator.add_sigchain_reflections

`Simulator.add_sigchain_reflections(ants=None, **kwargs)`

Apply reflection gains to the visibilities. See [add\(\)](#) for more details.

hera_sim.simulate.Simulator.add_xtalk

`Simulator.add_xtalk(model='gen_whitenoise_xtalk', bls=None, **kwargs)`

Add crosstalk to the visibilities. See [add\(\)](#) for more details.

hera_sim.simulate.Simulator.apply_defaults

Simulator.**apply_defaults**(*config*, *refresh*=True)

hera_sim.simulate.Simulator.chunk_sim_and_save

Simulator.**chunk_sim_and_save**(*save_dir*, *ref_files*=None, *Nint_per_file*=None, *prefix*=None, *sky_cmp*=None, *state*=None, *filetype*='uvh5', *clobber*=True)
Chunk a simulation in time and write to disk.

This function is a thin wrapper around `io.chunk_sim_and_save()`; please see that function's documentation for more information.

hera_sim.simulate.Simulator.get

Simulator.**get**(*component*, *ant1*=None, *ant2*=None, *pol*=None)

hera_sim.simulate.Simulator.plot_array

Simulator.**plot_array**()

Generate a plot of the array layout in ENU coordinates.

hera_sim.simulate.Simulator.refresh

Simulator.**refresh**()

Refresh the Simulator object.

This zeros the data array, resets the history, and clears the instance's `_components` dictionary.

hera_sim.simulate.Simulator.run_sim

Simulator.**run_sim**(*sim_file*=None, ***sim_params*)

hera_sim.simulate.Simulator.write

Simulator.**write**(*filename*, *save_format*='uvh5', ***kwargs*)

Attributes

antpos

freqs

Frequencies in GHz.

lsts

times

Return unique simulation times.

hera_sim.simulate.Simulator.antpos

property Simulator.antpos

hera_sim.simulate.Simulator.freqs

property Simulator.freqs

Frequencies in GHz.

hera_sim.simulate.Simulator.lsts

property Simulator.lst

hera_sim.simulate.Simulator.times

property Simulator.times

Return unique simulation times.

hera_sim.utils

Utility module

Functions

Jy2T(freqs, omega_p)

<i>calc_max_fringe_rate(freqs, ew_bl_len_ns)</i>	Calculate the max fringe-rate seen by an East-West baseline.
<i>compute_ha(lst, ra)</i>	Compute hour angle from local sidereal time and right ascension.
<i>gen_delay_filter(freqs, bl_len_ns[...])</i>	Generate a delay filter in delay space.
<i>gen_fringe_filter(lst, freqs, ew_bl_len_ns)</i>	Generate a fringe rate filter in fringe-rate & freq space.
<i>gen_white_noise([size])</i>	Produce complex Gaussian noise with unity variance.
<i>get_bl_len_magnitude(bl_len_ns)</i>	Get the magnitude of the length of the given baseline.
<i>jansky_to_kelvin(freqs, omega_p)</i>	Return Kelvin -> Jy conversion as a function of frequency.
<i>rough_delay_filter(data[, freqs, bl_len_ns, ...])</i>	A rough low-pass delay filter of data array along last axis.
<i>rough_fringe_filter(data[, lsts, freqs, ...])</i>	A rough fringe rate filter of data along zeroth axis.

hera_sim.utils.Jy2T

```
hera_sim.utils.Jy2T(freqs, omega_p)
```

hera_sim.utils.calc_max_fringe_rate

```
hera_sim.utils.calc_max_fringe_rate(freqs: numpy.ndarray, ew_bl_len_ns: float) → numpy.ndarray
```

Calculate the max fringe-rate seen by an East-West baseline.

Parameters

- **freqs** – Frequency array [GHz] **ew_bl_len_ns** (float): projected East-West baseline length [ns]
- **ew_bl_len_ns** – The EW baseline length, in nanosec.

Returns *fr_max* – Maximum fringe rate [Hz]

hera_sim.utils.compute_ha

```
hera_sim.utils.compute_ha(lsts: numpy.ndarray, ra: float) → numpy.ndarray
```

Compute hour angle from local sidereal time and right ascension.

Parameters

- **lst**s – Local sidereal times of the observation to be generated [radians]. Shape=(NTIMES,)
- **ra** – The right ascension of a point source [radians].

Returns *ha* – Hour angle corresponding to the provide ra and times. Shape=(NTIMES,)

hera_sim.utils.gen_delay_filter

```
hera_sim.utils.gen_delay_filter(freqs: numpy.ndarray, bl_len_ns: [float, numpy.ndarray], standoff: float = 0.0, delay_filter_type: Optional[str] = 'gauss', min_delay: Optional[float] = None, max_delay: Optional[float] = None, normalize: Optional[float] = None) → numpy.ndarray
```

Generate a delay filter in delay space.

Parameters

- **freqs** – Frequency array [GHz]
- **bl_len_ns** – The baseline length in nanosec (i.e. $1e9 * \text{metres} / c$). If scalar, interpreted as E-W length, if len(2), interpreted as EW and NS length, otherwise the full [EW, NS, Z] length. Unspecified dimensions are assumed to be zero.
- **standoff** – Supra-horizon buffer [nanosec]
- **delay_filter_type** – Options are ['gauss', 'trunc_gauss', 'tophat', 'none']. This sets the filter profile. gauss has a 1-sigma as horizon (+ standoff) divided by four, trunc_gauss is same but truncated above 1-sigma. 'none' means filter is identically one.
- **min_delay** – Minimum absolute delay of filter

- **max_delay** – Maximum absolute delay of filter
- **normalize** – If set, will normalize the filter such that the power of the output matches the power of the input times the normalization factor. If not set, the filter merely has a maximum of unity.

Returns `delay_filter` – Delay filter in delay space (1D)

hera_sim.utils.gen_fringe_filter

```
hera_sim.utils.gen_fringe_filter(lsts: numpy.ndarray, freqs: numpy.ndarray, ew_bl_len_ns:  
float, fringe_filter_type: Optional[str] = 'tophat', **filter_kwargs) → numpy.ndarray
```

Generate a fringe rate filter in fringe-rate & freq space.

Parameters

- **lst**s – lst array [radians]
- **freqs** – Frequency array [GHz]
- **ew_bl_len_ns** – Projected East-West baseline length [nanosec]
- **fringe_filter_type** – Options ['tophat', 'gauss', 'custom', 'none']

Other Parameters

- Other parameters are specific to each ``filter_type``.
- For ``filter_type == 'gauss'`` –
 - `fr_width` (float or array): Sets gaussian width in fringe-rate [Hz]
- For ``filter_type == 'custom'`` –
 - `FR_filter` (ndarray): shape (Nfrates, Nfreqs) with custom filter (must be fft-shifted, see below)
 - `FR_frates` (ndarray): array of FR_filter fringe rates [Hz] (must be monotonically increasing)
 - `FR_freqs` (ndarray): array of FR_filter freqs [GHz]

Returns `fringe_filter` – 2D array in fringe-rate & freq space

Notes

If `filter_type == 'tophat'` filter is a tophat out to max fringe-rate set by `ew_bl_len_ns`.

If `filter_type == 'gauss'` filter is a Gaussian centered on max fringe-rate with width set by kwarg `fr_width` in Hz

If `filter_type == 'custom'` filter is a custom 2D (Nfrates, Nfreqs) filter fed as 'FR_filter' its fringe-rate array is fed as "FR_frates" in Hz, its freq array is fed as "FR_freqs" in GHz. Note that input `FR_filter` must be fft-shifted along axis 0, but output filter is `ifftshift`-ed back along axis 0.

If `filter_type == 'none'` fringe filter is identically one.

hera_sim.utils.gen_white_noise

```
hera_sim.utils.gen_white_noise(size: [<class 'int'>, typing.Tuple[int]] = 1) → numpy.ndarray  
    Produce complex Gaussian noise with unity variance.
```

Parameters `size` – Shape of output array. Can be an integer if a single dimension is required, otherwise a tuple of ints.

Returns `noise` – White noise realization with specified shape.

hera_sim.utils.get_bl_len_magnitude

```
hera_sim.utils.get_bl_len_magnitude(bl_len_ns: [<class 'float'>, <class 'numpy.ndarray'>,  
                                                typing.Sequence]) → float  
    Get the magnitude of the length of the given baseline.
```

Parameters `bl_len_ns` – The baseline length in nanosec (i.e. $1e9 * \text{metres} / c$). If scalar, interpreted as E-W length, if len(2), interpreted as EW and NS length, otherwise the full [EW, NS, Z] length. Unspecified dimensions are assumed to be zero.

Returns `mag` – The magnitude of the baseline length.

hera_sim.utils.jansky_to_kelvin

```
hera_sim.utils.jansky_to_kelvin(freqs: numpy.ndarray, omega_p: [<class  
                                                               'hera_sim.interpolators.Beam'>, <class 'numpy.ndarray'>])  
                                         → numpy.ndarray  
    Return Kelvin -> Jy conversion as a function of frequency.
```

Parameters

- `freqs` – Frequencies for which to calculate the conversion. Units of GHz.
- `omega_p` – Beam area as a function of frequency. Must have the same shape as `freqs` if an ndarray. Otherwise, must be an interpolation object which converts frequencies (in GHz) to beam size.

Returns `Jy_to_K` – Array for converting Jy to K, same shape as `freqs`.

hera_sim.utils.rough_delay_filter

```
hera_sim.utils.rough_delay_filter(data: numpy.ndarray, freqs: Optional[numpy.ndarray] =  
                                         None, bl_len_ns: Optional[numpy.ndarray] = None, *, delay_filter: Optional[numpy.ndarray] = None, **kwargs) →  
                                         numpy.ndarray
```

A rough low-pass delay filter of data array along last axis.

Parameters

- `data` – Data to be filtered along last axis
- `freqs` – Frequencies of the filter [GHz]
- `bl_len_ns` – The baseline length (see `gen_delay_filter()`).
- `delay_filter` – The pre-computed filter to use. A filter can be created on-the-fly by passing `kwargs`.

Other Parameters All other parameters passed to :func:`gen_delay_filter`.

Returns *filt_data* – Filtered data array (same shape as *data*).

hera_sim.utils.rough_fringe_filter

```
hera_sim.utils.rough_fringe_filter(data: numpy.ndarray, lsts: Optional[numpy.ndarray]
                                    = None, freqs: Optional[numpy.ndarray] = None,
                                    ew_bl_len_ns: Optional[float] = None, *, fringe_filter:
                                    Optional[numpy.ndarray] = None, **kwargs) →
                                    numpy.ndarray
```

A rough fringe rate filter of data along zeroth axis.

Parameters

- **data** – data to filter along zeroth axis
- **fringe_filter** – A pre-computed fringe-filter to use. Computed on the fly if not given.

Other Parameters

- All other parameters passed to :func:`gen_fringe_filter` to compute the fringe
- filter on the fly (if necessary). If so, at least ``lsts``, ``freqs``, and
- ``ew_bl_len_ns`` are required.

Returns *filt_data* – Filtered data (same shape as *data*).

1.3.2 Visibility Simulators

hera_sim.visibilities.simulators

hera_sim.visibilities.conversions

A number of mappings which may be useful for visibility simulators.

hera_sim.visibilities.vis_cpu

hera_sim.visibilities.simulators

Classes

VisibilitySimulator([obsparams, uvdata, ...])

hera_sim.visibilities.simulators.VisibilitySimulator

```
class hera_sim.visibilities.simulators.VisibilitySimulator(obsparams=None,  
                                         uvdata=None,  
                                         sky_freqs=None,  
                                         beams=None,  
                                         beam_ids=None,  
                                         sky_intensity=None,  
                                         point_source_pos=None,  
                                         point_source_flux=None,  
                                         nside=32)
```

Methods

```
__init__([obsparams, uvdata, sky_freqs, ...])
```

Parameters

- **obsparams** (*dict or filepath, optional*) – Exactly the expected input to *pyuvsim*'s

<code>convert_healpix_to_point_sources(hmap)</code>	Convert a HEALPix map to a set of point sources.
<code>convert_point_sources_to_healpix(...[, nside])</code>	Convert point sources to an approximate diffuse HEALPix model.
<code>simulate()</code>	Perform the visibility simulation.
<code>validate()</code>	Checks for correct input format.
<code>write_config_file(filename[, direc, ...])</code>	Writes a YAML config file corresponding to the current UVData object.

hera_sim.visibilities.simulators.VisibilitySimulator.__init__

```
VisibilitySimulator.__init__(obsparams=None,      uvdata=None,      sky_freqs=None,  
                            beams=None,      beam_ids=None,      sky_intensity=None,  
                            point_source_pos=None,    point_source_flux=None,  
                            nside=32)
```

Parameters

- **obsparams** (*dict or filepath, optional*) – Exactly the expected input to *pyuvsim*'s `pyuvsim.simsetup.initialize_uvdata_from_params()` function. By default *uvdata*, *beams*, and *beam_ids* are used instead.
- **uvdata** (*UVData object, optional*) – A `pyuvdata.UVData` object contain information about the “observation”. Initialized from *obsparams*, if included.
- **sky_freqs** (*array_like, optional*) – Frequencies at which the sky intensity and/or point sources are defined in [Hz]. Defaults to the unique frequencies in *uvdata* Shape=(NFREQS,).
- **beams** (*array_like of pyuvsim.analyticbeam.AnalyticBeam,*) – optional UVBeam models for as many antennae as have unique beams. Initialized from *obsparams*, if included. Defaults to a single uniform beam is applied for every antenna. Each beam is the response of an individual antenna and NOT a per-baseline response. Shape=(N_BEAMS,).

- **beam_ids** (*array_like of int, optional*) – List of integers specifying which beam model each antenna uses (i.e. the index of *beams* which it should refer to). Initialized from *obsparams*, if included. By default, all antennas use the same beam (beam 0). Shape=(N_ANTS,).
- **sky_intensity** (*array_like, optional*) – A healpix model for the intensity of the sky emission, in [Jy/sr]. Shape=(NFREQS, N_PIX_SKY).
- **point_source_pos** (*array_like, optional*) – An array of point sources. For each source, the entries are (ra, dec) [rad] (assumed to be in J2000). Shape=(N_SOURCES, 2).
- **point_source_flux** (*array_like, optional*) – An array of fluxes of the given point sources, per frequency. Fluxes in [Jy]. Shape=(NFREQS, N_SOURCES).
- **nside** (*int, optional*) – Only used if sky_intensity is *not* given but the simulator is incapable of directly dealing with point sources. In this case, it sets the resolution of the healpix map to which the sources will be allocated.

Notes

Input beam models represent the responses of individual antennas and are NOT the same as per-baseline “primary beams”. This interpretation of a “primary beam” would be the product of the responses of two input antenna beams.

`hera_sim.visibilities.simulators.VisibilitySimulator.convert_healpix_to_point_sources`

```
static VisibilitySimulator.convert_healpix_to_point_sources(hmap)
```

Convert a HEALPix map to a set of point sources.

The point sources are placed at the center of each pixel.

Parameters `hmap` (*array_like*) – The HEALPix map. Shape=(NFREQ, NPIX).

Returns *array_like* – The point source approximation. Positions in (ra, dec) (J2000). Shape=(N_SOURCES, 2). Fluxes in [Jy]. Shape=(NFREQ, N_SOURCES).

`hera_sim.visibilities.simulators.VisibilitySimulator.convert_point_sources_to_healpix`

```
static VisibilitySimulator.convert_point_sources_to_healpix(point_source_pos,
                                                               point_source_flux,
                                                               nside=32)
```

Convert point sources to an approximate diffuse HEALPix model.

The healpix map returned is in RING scheme.

Parameters

- **point_source_pos** (*array_like*) – An array of point sources. For each source, the entries are (ra, dec) [rad] (assumed to be in J2000). Shape=(N_SOURCES, 2).
- **point_source_flux** (*array_like*) – `point_source_flux` : *array_like*, optional An array of fluxes of the given point sources, per frequency. Fluxes in [Jy]. Shape=(NFREQS, N_SOURCES).
- **nside** (*int, optional*) – HEALPix nside parameter (must be a power of 2).

Returns *array_like* – The HEALPix diffuse model. Shape=(NFREQ, NPIX).

hera_sim.visibilities.simulators.VisibilitySimulator.simulate

VisibilitySimulator.**simulate**()

Perform the visibility simulation.

hera_sim.visibilities.simulators.VisibilitySimulator.validate

VisibilitySimulator.**validate**()

Checks for correct input format.

hera_sim.visibilities.simulators.VisibilitySimulator.write_config_file

VisibilitySimulator.**write_config_file**(filename, direc='.', beam_filepath=None, antenna_layout_path=None)

Writes a YAML config file corresponding to the current UVData object.

Parameters

- **filename** (*str*) – Filename of the config file.
- **direc** (*str*) – Directory in which to place the config file and its supporting files.
- **beam_filepath** (*str, optional*) – Where to put the beam information. Default is to place it alongside the config file, but with extension ‘.beams’.
- **antenna_layout_path** (*str, optional*) – Where to put the antenna layout CSV file. Default is alongside the main config file, but appended with ‘_antenna_layout.csv’.

Attributes

diffuse_ability

n_ant

Number of antennas in array.

n_beams

Number of beam models used.

n_pix

Number of pixels in the sky map.

nside

Nside parameter of the sky healpix map.

point_source_ability

hera_sim.visibilities.simulators.VisibilitySimulator.diffuse_ability

VisibilitySimulator.**diffuse_ability** = **True**

hera_sim.visibilities.simulators.VisibilitySimulator.n_ant**VisibilitySimulator.n_ant**

Number of antennas in array.

hera_sim.visibilities.simulators.VisibilitySimulator.n_beams**VisibilitySimulator.n_beams**

Number of beam models used.

hera_sim.visibilities.simulators.VisibilitySimulator.n_pix**VisibilitySimulator.n_pix**

Number of pixels in the sky map.

hera_sim.visibilities.simulators.VisibilitySimulator.nside**property VisibilitySimulator.nside**

Nside parameter of the sky healpix map.

hera_sim.visibilities.simulators.VisibilitySimulator.point_source_ability**VisibilitySimulator.point_source_ability = True****hera_sim.visibilities.conversions**

A number of mappings which may be useful for visibility simulators.

Functions

<code>eq2top_m(ha, dec)</code>	Calculates the equatorial to topocentric conversion matrix.
<code>healpix_to_crd_eq(h[, nest])</code>	Determine equatorial co-ordinates of a healpix map's pixels.
<code>uvbeam_to_lm(uvbeam, freqs[, n_pix_lm])</code>	Convert a UVbeam to a uniform (l,m) grid

hera_sim.visibilities.conversions.eq2top_m`hera_sim.visibilities.conversions.eq2top_m(ha, dec)`

Calculates the equatorial to topocentric conversion matrix.

Conversion at a given hour angle (ha) and declination (dec). Ripped straight from aipy.

Parameters

- **ha** (*float*) – Hour angle [rad].
- **dec** (*float*) – Declination [rad].

Returns `ndarray` – Coordinate transform matrix converting equatorial coordinates to topocentric coordinates. Shape=(3, 3).

hera_sim.visibilities.conversions.healpix_to_crd_eq

`hera_sim.visibilities.conversions.healpix_to_crd_eq(h, nest=False)`
Determine equatorial co-ordinates of a healpix map's pixels.

Parameters

- **h** (*array_like*) – The HEALPix array. Shape=(12*N^2,) for integer N.
 - **nest** (*bool, optional*) – Whether to use the NEST configuration for the HEALPix array.

Returns `ndarray` – The equatorial coordinates of each HEALPix pixel. Shape=($12 * N^2$, 3) for integer N .

```
hera sim.visibilities.conversions.uvbeam to Im
```

Convert a UVbeam to a uniform (1,m) grid

Parameters

- **uvbeam** (*UVBeam object*) – Beam to convert to an (l, m) grid.
 - **freqs** (*array_like*) – Frequencies to interpolate to in [Hz]. Shape=(NFREQS,).
 - **n_npix_lm** (*int, optional*) – Number of pixels for each side of the beam grid. Default is 63.

Returns *ndarray* – The beam map cube. Shape=(NFREQS, BEAM_PIX, BEAM_PIX).

hera sim.visibilities.vis cpu

Functions

`vis_cpv(antpos, freq, eq2tops, crd_eq, ...)` Calculate visibility from an input intensity map and beam model.

hera sim.visibilities.vis cpu.vis cpu

```
hera_sim.visibilities.vis_cpu.vis_cpu(antpos, freq, eq2tops, crd_eq, I_sky, bm_cube, precision=1)
```

Calculate visibility from an input intensity map and beam model.

Provided as a standalone function.

Parameters

- **antpos** (*array_like*) – Antenna position array. Shape=(NANT, 3).
 - **freq** (*float*) – Frequency to evaluate the visibilities at [GHz].
 - **eq2tops** (*array_like*) – Set of 3x3 transformation matrices converting equatorial coordi-

nates to topocentric at each hour angle (and declination) in the dataset. Shape=(NTIMES, 3, 3).

- **crd_eq** (*array_like*) – Equatorial coordinates of Healpix pixels, in Cartesian system. Shape=(3, NPIX).
- **I_sky** (*array_like*) – Intensity distribution on the sky, stored as array of Healpix pixels. Shape=(NPIX,).
- **bm_cube** (*array_like*) – Beam maps for each antenna. Shape=(NANT, BM_PIX, BM_PIX).
- **real_dtype** {np.float32, np.float64} – Data type to use for real-valued arrays.
- **complex_dtype** {np.complex64, np.complex128} – Data type to use for complex-valued arrays.

Returns *array_like* – Visibilities. Shape=(NTIMES, NANTS, NANTS).

Classes

<code>VisCPU([bm_pix, precision, use_gpu])</code>	vis_cpu visibility simulator.
---	-------------------------------

hera_sim.visibilities.vis_cpu.VisCPU

```
class hera_sim.visibilities.vis_cpu.VisCPU(bm_pix=100, precision=1, use_gpu=False,
                                            **kwargs)
```

vis_cpu visibility simulator.

This is a fast, simple visibility simulator that is intended to be replaced by vis_gpu. It extends VisibilitySimulator.

Methods

`__init__([bm_pix, precision, use_gpu])`

Parameters

- **bm_pix** (*int, optional*) – The number of pixels along a side in the beam map when

`convert_healpix_to_point_sources(hmap)` Convert a HEALPix map to a set of point sources.

`convert_point_sources_to_healpix(...[, nside])` Convert point sources to an approximate diffuse HEALPix model.

`get_beam_lm()` Obtain the beam pattern in (l,m) co-ordinates for each antenna.

`get_diffuse_crd_eq()` Calculate equatorial coords of HEALPix sky pixels (Cartesian).

`get_eq2tops()` Calculate transformations from equatorial to topocentric coords.

`get_point_source_crd_eq()` Calculate approximate HEALPix map of point sources.

`simulate()` Perform the visibility simulation.

continues on next page

Table 61 – continued from previous page

<code>validate()</code>	Checks for correct input format.
<code>write_config_file(filename[, direc, ...])</code>	Writes a YAML config file corresponding to the current UVData object.

hera_sim.visibilities.vis_cpu.VisCPU.__init__

`VisCPU.__init__(bm_pix=100, precision=1, use_gpu=False, **kwargs)`

Parameters

- **bm_pix** (*int, optional*) – The number of pixels along a side in the beam map when converted to (l, m) coordinates. Defaults to 100.
- **real_dtype** (*{np.float32, np.float64}*) – Data type for real-valued arrays.
- **complex_dtype** (*{np.complex64, np.complex128}*) – Data type for complex-valued arrays.
- ****kwargs** – Arguments of VisibilitySimulator.

hera_sim.visibilities.vis_cpu.VisCPU.convert_healpix_to_point_sources

`static VisCPU.convert_healpix_to_point_sources(hmap)`

Convert a HEALPix map to a set of point sources.

The point sources are placed at the center of each pixel.

Parameters `hmap (array_like)` – The HEALPix map. Shape=(NFREQ, NPIX).

Returns `array_like` – The point source approximation. Positions in (ra, dec) (J2000). Shape=(N_SOURCES, 2). Fluxes in [Jy]. Shape=(NFREQ, N_SOURCES).

hera_sim.visibilities.vis_cpu.VisCPU.convert_point_sources_to_healpix

`static VisCPU.convert_point_sources_to_healpix(point_source_pos, point_source_flux, nside=32)`

Convert point sources to an approximate diffuse HEALPix model.

The healpix map returned is in RING scheme.

Parameters

- **point_source_pos** (*array_like*) – An array of point sources. For each source, the entries are (ra, dec) [rad] (assumed to be in J2000). Shape=(N_SOURCES, 2).
- **point_source_flux** (*array_like*) – `point_source_flux : array_like, optional` An array of fluxes of the given point sources, per frequency. Fluxes in [Jy]. Shape=(NFREQS, N_SOURCES).
- **nside** (*int, optional*) – HEALPix nside parameter (must be a power of 2).

Returns `array_like` – The HEALPix diffuse model. Shape=(NFREQ, NPIX).

hera_sim.visibilities.vis_cpu.VisCPU.get_beam_lm

VisCPU.**get_beam_lm()**

Obtain the beam pattern in (l,m) co-ordinates for each antenna.

Returns *array_like* – The beam pattern in (l,m) for each antenna. Shape=(NANT, BM_PIX, BM_PIX).

Notes

Due to using the verbatim `vis_cpu()` function, the beam cube must have an entry for each antenna, which is a bit of a waste of memory in some cases. If this is changed in the future, this method can be modified to only return one matrix for each beam.

hera_sim.visibilities.vis_cpu.VisCPU.get_diffuse_crd_eq

VisCPU.**get_diffuse_crd_eq()**

Calculate equatorial coords of HEALPix sky pixels (Cartesian).

Returns *array_like of self._real_dtype* – The equatorial co-ordinates of each pixel. Shape=(12*NPIX^2, 3).

hera_sim.visibilities.vis_cpu.VisCPU.get_eq2tops

VisCPU.**get_eq2tops()**

Calculate transformations from equatorial to topocentric coords.

Returns *array_like of self._real_dtype* – The set of 3x3 transformation matrices converting equatorial to topocentric co-ordinates at each LST. Shape=(NTIMES, 3, 3).

hera_sim.visibilities.vis_cpu.VisCPU.get_point_source_crd_eq

VisCPU.**get_point_source_crd_eq()**

Calculate approximate HEALPix map of point sources.

Returns *array_like* – equatorial coordinates of Healpix pixels, in Cartesian system. Shape=(3, NPIX).

hera_sim.visibilities.vis_cpu.VisCPU.simulate

VisCPU.**simulate()**

Perform the visibility simulation.

hera_sim.visibilities.vis_cpu.VisCPU.validate

VisCPU.**validate**()

Checks for correct input format.

hera_sim.visibilities.vis_cpu.VisCPU.write_config_file

VisCPU.**write_config_file**(filename, direc='.', beam_filepath=None, antenna_layout_path=None)

Writes a YAML config file corresponding to the current UVData object.

Parameters

- **filename** (*str*) – Filename of the config file.
- **direc** (*str*) – Directory in which to place the config file and its supporting files.
- **beam_filepath** (*str; optional*) – Where to put the beam information. Default is to place it alongside the config file, but with extension ‘.beams’.
- **antenna_layout_path** (*str; optional*) – Where to put the antenna layout CSV file. Default is alongside the main config file, but appended with ‘_antenna_layout.csv’.

Attributes

diffuse_ability

<i>lst</i> s	Sets LSTs from uvdata if not already set.
--------------	---

<i>n_ant</i>	Number of antennas in array.
--------------	------------------------------

<i>n_beams</i>	Number of beam models used.
----------------	-----------------------------

<i>n_pix</i>	Number of pixels in the sky map.
--------------	----------------------------------

<i>nside</i>	Nside parameter of the sky healpix map.
--------------	---

point_source_ability

hera_sim.visibilities.vis_cpu.VisCPU.diffuse_ability

VisCPU.**diffuse_ability** = True

hera_sim.visibilities.vis_cpu.VisCPU.lsts**property VisCPU.lsts**

Sets LSTs from uvdata if not already set.

Returns *array-like* – LSTs of observations. Shape=(NTIMES,).**hera_sim.visibilities.vis_cpu.VisCPU.n_ant****VisCPU.n_ant**

Number of antennas in array.

hera_sim.visibilities.vis_cpu.VisCPU.n_beams**VisCPU.n_beams**

Number of beam models used.

hera_sim.visibilities.vis_cpu.VisCPU.n_pix**VisCPU.n_pix**

Number of pixels in the sky map.

hera_sim.visibilities.vis_cpu.VisCPU.nside**property VisCPU.nside**

Nside parameter of the sky healpix map.

hera_sim.visibilities.vis_cpu.VisCPU.point_source_ability**VisCPU.point_source_ability = True**

1.4 Contributing

Contributions are welcome, and they are greatly appreciated! Every little bit helps, and credit will always be given.

1.4.1 Bug reports

When reporting a bug please include:

- Your operating system name and version.
- Any details about your local setup that might be helpful in troubleshooting.
- Detailed steps to reproduce the bug.

1.4.2 Documentation improvements

hera_sim could always use more documentation, whether as part of the official hera_sim docs or in docstrings.

1.4.3 Feature requests and feedback

The best way to send feedback is to file an issue at https://github.com/HERA-Team/hera_sim/issues.

If you are proposing a feature:

- Explain in detail how it would work.
- Keep the scope as narrow as possible, to make it easier to implement.
- Remember that this is a volunteer-driven project, and that code contributions are welcome :)

1.4.4 Development

To set up hera_sim for local development:

1. If you are *not* on the HERA-Team collaboration, make a fork of hera_sim (look for the “Fork” button).
2. Clone the repository locally. If you made a fork in step 1:

```
git clone git@github.com:your_name_here/hera_sim.git
```

Otherwise:

```
git clone git@github.com:HERA-Team/hera_sim.git
```

3. Create a branch for local development (you will *not* be able to push to “master”):

```
git checkout -b name-of-your-bugfix-or-feature
```

Now you can make your changes locally.

4. Make a development environment. We highly recommend using conda for this. With conda, just run:

```
conda env create -f travis-environment.yml
```

4. When you’re done making changes, run all the checks, doc builder and spell checker with tox one command:

```
tox
```

5. Commit your changes and push your branch to GitHub:

```
git add .
git commit -m "Your detailed description of your changes."
git push origin name-of-your-bugfix-or-feature
```

6. Submit a pull request through the GitHub website.

Pull Request Guidelines

If you need some code review or feedback while you're developing the code just make the pull request.

For merging, you should:

1. Include passing tests (run tox)¹.
2. Update documentation when there's new API, functionality etc.
3. Add a note to CHANGELOG.rst about the changes.
4. Add yourself to AUTHORS.rst.

1.5 Developing hera_sim

hera_sim broadly follows the best-practices laid out in XXX.

Todo: where is that best-practices doc?

All docstrings should be written in Google docstring format.

1.6 AUTHORS

- HERA-Team - <https://github.com/HERA-Team>

1.7 Changelog

1.7.1 v1.0.0 [???

Added

Fixed

Changed

- All functions that take frequencies and LSTs as arguments have had their signatures changed to func(lsts, freqs, *args, **kwargs)
- Changes to handling of functions which employ a fringe or delay filtering step with variable keywords for the filters used. Filter keywords are now specified with individual dictionaries called `delay_filter_kwargs` or `fringe_filter_kwargs`, depending on the filter used.

– Functions affected by this change are as follows:

- * `diffuse_foreground`
- * `noiselike_eor`

¹ If you don't have all the necessary python versions available locally you can rely on Travis - it will run the tests for each change you add in the pull request.

It will be slower though ...

- Changes to parameters that shared the same name but represented conceptually different objects in various functions. Functions affected by this are as follows:
 - `utils.rough_delay_filter`
 - `utils.rough_fringe_filter`
 - Most RFI functions
- The `io.empty_uvdata` function had its default keyword values set to `None`. The keywords accepted by this function have also been changed to match their names in `pyuvsim.simsetup.initialize_uvdata_from_keywords`
- Changes to parameters in most RFI models. Optional parameters that are common to many models (but should not share the same name), such as `std` or `chance`, have been prefixed with the model name and an underscore (e.g. `dtv_chance`). Various other parameters have been renamed for consistency/clarity. Note that the `freq_min` and `freq_max` parameters for `rfi_dtv` have been replaced by the single parameter `dtv_band`, which is a tuple denoting the edges of the DTV band in GHz.
- Functions in `utils` now use `freqs` instead of `fqs`.

1.7.2 v0.3.0 [2019.12.10]

Added

- New sub-package `simulators`
 - **VisibilitySimulators class**
 - * Provides a common interface to interferometric visibility simulators. Users instantiate one of its subclasses and provide input antenna and sky scenarios.
 - * `HealVis` subclass
 - * Provides an interface to the `healvis` visibility simulator.
 - **VisCPU subclass**
 - * Provides an interface to the `viscpu` visibility simulator.
 - **conversions module**
 - * Not intended to be interfaced with by the end user; it provides useful coordinate transformations for `VisibilitySimulators`.

1.7.3 v0.2.0 [2019.11.20]

Added

- **Command-line Interface**
 - Use anywhere with `hera_sim run [options] INPUT`
 - Tutorial available on [readthedocs](#)
- **Enhancement of `run_sim` method of `Simulator` class**
 - **Allows for each simulation component to be returned**
 - * Components returned as a list of 2-tuples (`model_name, visibility`)
 - * Components returned by specifying `ret_vis=True` in their kwargs

- **Option to seed random number generators for various methods**
 - Available via the `Simulator.add_` methods by specifying the kwarg `seed_redundantly=True`
 - Seeds are stored in `Simulator` object, and may be saved as a `.npz` file when using the `Simulator.write_data` method
- **New YAML tag `!antpos`**
 - Allows for antenna layouts to be constructed using `hera_sim.antpos` functions by specifying parameters in config file

Fixed

- Changelog formatting for v0.1.0 entry

Changed

- **Implementation of `defaults` module**
 - Allows for semantic organization of config files
 - **Parameters that have the same name take on the same value**
 - * e.g. `std` in various `rfi` functions only has one value, even if it's specified multiple times

1.7.4 v0.1.0 [2019.08.28]

Added

- **New module `interpolators`**
 - Classes intended to be interfaced with by end-users:
 - * **Tsky**
 - Provides an interface for generating a sky temperature interpolation object when provided with a `.npz` file and interpolation kwargs.
 - * **Beam, Bandpass**
 - Provides an interface for generating either a `poly1d` or `interp1d` interpolation object when provided with an appropriate datafile.
- **New module `defaults`**
 - Provides an interface which allows the user to dynamically adjust default parameter settings for various `hera_sim` functions.
- **New module `__yaml_constructors`**
 - Not intended to be interfaced with by the end user; this module just provides a location for defining new YAML tags to be used in conjunction with the `defaults` module features and the `Simulator.run_sim` method.
- **New directory `config`**
 - Provides a location to store configuration files.

Fixed

Changed

- HERA-specific variables had their definitions removed from the codebase. Objects storing these variables still exist in the codebase, but their definitions now come from loading in data stored in various new files added to the `data` directory.

1.7.5 v0.0.1

- Initial released version

**CHAPTER
TWO**

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

h

hera_sim.antpos, 38
hera_sim.defaults, 40
hera_sim.eor, 40
hera_sim.foregrounds, 41
hera_sim.interpolators, 44
hera_sim.io, 48
hera_sim.noise, 49
hera_sim.rfi, 51
hera_sim.sigchain, 54
hera_sim.simulate, 60
hera_sim.utils, 63
hera_sim.vis, 38
hera_sim.visibilities.conversions, 71
hera_sim.visibilities.simulators, 67
hera_sim.visibilities.vis_cpu, 72

INDEX

Symbols

`__init__()` (*hera_sim.antpos.HexArray method*), 39
`__init__()` (*hera_sim.antpos.LinearArray method*), 40
`__init__()` (*hera_sim.eor.NoiselikeEoR method*), 41
`__init__()` (*hera_sim.foregrounds.DiffuseForeground method*), 42
`__init__()` (*hera_sim.foregrounds.PointSourceForeground method*), 43
`__init__()` (*hera_sim.interpolators.Bandpass method*), 44
`__init__()` (*hera_sim.interpolators.Beam method*), 45
`__init__()` (*hera_sim.interpolators.FreqInterpolator method*), 45
`__init__()` (*hera_sim.interpolators.Interpolator method*), 46
`__init__()` (*hera_sim.interpolators.Tsky method*), 46
`__init__()` (*hera_sim.noise.ThermalNoise method*), 50
`__init__()` (*hera_sim.rfi.DTV method*), 51
`__init__()` (*hera_sim.rfi.Impulse method*), 52
`__init__()` (*hera_sim.rfi.RfiStation method*), 53
`__init__()` (*hera_sim.rfi.Scatter method*), 53
`__init__()` (*hera_sim.rfi.Stations method*), 54
`__init__()` (*hera_sim.sigchain.Bandpass method*), 56
`__init__()` (*hera_sim.sigchain.CrossCouplingCrosstalk method*), 57
`__init__()` (*hera_sim.sigchain.CrossCouplingSpectrum method*), 58
`__init__()` (*hera_sim.sigchain.Reflections method*), 58
`__init__()` (*hera_sim.sigchain.WhiteNoiseCrosstalk method*), 59
`__init__()` (*hera_sim.simulate.Simulator method*), 60
`__init__()` (*hera_sim.visibilities.simulators.VisibilitySimulator method*), 68
`__init__()` (*hera_sim.visibilities.vis_cpu.VisCPU method*), 74
`add()` (*hera_sim.simulate.Simulator method*), 61
`add_eor()` (*hera_sim.simulate.Simulator method*), 61
`add_foregrounds()` (*hera_sim.simulate.Simulator method*), 61
`add_gains()` (*hera_sim.simulate.Simulator method*), 61
`add_noise()` (*hera_sim.simulate.Simulator method*), 61
`add_rfi()` (*hera_sim.simulate.Simulator method*), 61
`add_sigchain_reflections()` (*hera_sim.simulate.Simulator method*), 61
`add_xtalk()` (*hera_sim.simulate.Simulator method*), 61
`antpos()` (*hera_sim.simulate.Simulator property*), 63
`apply_defaults()` (*hera_sim.simulate.Simulator method*), 62
`apply_gains()` (*in module hera_sim.sigchain*), 54

B

`Bandpass` (*class in hera_sim.interpolators*), 44
`Bandpass` (*class in hera_sim.sigchain*), 56
`Beam` (*class in hera_sim.interpolators*), 45

C

`calc_max_fringe_rate()` (*in module hera_sim.utils*), 64
`chunk_sim_and_save()` (*hera_sim.simulate.Simulator method*), 62
`chunk_sim_and_save()` (*in module hera_sim.io*), 48
`compute_ha()` (*in module hera_sim.utils*), 64
`convert_healpix_to_point_sources()` (*hera_sim.visibilities.simulators.VisibilitySimulator static method*), 69
`convert_healpix_to_point_sources()` (*hera_sim.visibilities.vis_cpu.VisCPU static method*), 74
`convert_point_sources_to_healpix()` (*hera_sim.visibilities.simulators.VisibilitySimulator static method*), 69

<pre> convert_point_sources_to_healpix() (<i>hera_sim.visibilities.vis_cpu.VisCPU method</i>), 74 CrossCouplingCrosstalk (<i>hera_sim.sigchain</i>), 57 CrossCouplingSpectrum (<i>hera_sim.sigchain</i>), 57 </pre>	<pre> get_point_source_crd_eq() (<i>hera_sim.visibilities.vis_cpu.VisCPU method</i>), 75 </pre>
D	
<pre> diffuse_ability (<i>hera_sim.visibilities.simulators.VisibilitySimulator attribute</i>), 70 diffuse_ability (<i>hera_sim.visibilities.vis_cpu.VisCPU attribute</i>), 76 DiffuseForeground (<i>hera_sim.foregrounds</i>), 42 DTV (<i>class in hera_sim.rfi</i>), 51 </pre>	
E	
<pre> empty_uvdata () (<i>in module hera_sim.io</i>), 49 eq2top_m () (<i>in module hera_sim.visibilities.conversions</i>), 71 </pre>	
F	
<pre> FreqInterpolator (<i>class in hera_sim.interpolators</i>), 45 freqs () (<i>hera_sim.interpolators.Tsky property</i>), 47 freqs () (<i>hera_sim.simulate.Simulator property</i>), 63 </pre>	
G	
<pre> gen_bandpass () (<i>in module hera_sim.sigchain</i>), 55 gen_delay_filter () (<i>in module hera_sim.utils</i>), 64 gen_delay_phs () (<i>in module hera_sim.sigchain</i>), 55 gen_fringe_filter () (<i>in module hera_sim.utils</i>), 65 gen_reflection_coefficient () (<i>hera_sim.sigchain.CrossCouplingCrosstalk static method</i>), 57 gen_reflection_coefficient () (<i>hera_sim.sigchain.Reflections static method</i>), 59 gen_reflection_coefficient () (<i>in module hera_sim.sigchain</i>), 55 gen_white_noise () (<i>in module hera_sim.utils</i>), 66 get () (<i>hera_sim.simulate.Simulator method</i>), 62 get_beam_lm () (<i>hera_sim.visibilities.vis_cpu.VisCPU method</i>), 75 get_bl_len_magnitude () (<i>in module hera_sim.utils</i>), 66 get_diffuse_crd_eq () (<i>hera_sim.visibilities.vis_cpu.VisCPU method</i>), 75 get_eq2tops () (<i>hera_sim.visibilities.vis_cpu.VisCPU method</i>), 75 </pre>	
H	
<pre> healpix_to_crd_eq () (<i>in module hera_sim.visibilities.conversions</i>), 72 hera_sim.antpos (<i>module</i>), 38 hera_sim.defaults (<i>VisibilitySimulator module</i>), 40 hera_sim.eor (<i>module</i>), 40 hera_sim.foregrounds (<i>module</i>), 41 hera_sim.interpolators (<i>module</i>), 44 hera_sim.io (<i>module</i>), 48 hera_sim.noise (<i>module</i>), 49 hera_sim.rfi (<i>module</i>), 51 hera_sim.sigchain (<i>module</i>), 54 hera_sim.simulate (<i>module</i>), 60 hera_sim.utils (<i>module</i>), 63 hera_sim.vis (<i>module</i>), 38 hera_sim.visibilities.conversions (<i>module</i>), 71 hera_sim.visibilities.simulators (<i>module</i>), 67 hera_sim.visibilities.vis_cpu (<i>module</i>), 72 HexArray (<i>class in hera_sim.antpos</i>), 39 </pre>	
I	
<pre> Impulse (<i>class in hera_sim.rfi</i>), 52 Interpolator (<i>class in hera_sim.interpolators</i>), 46 is_multiplicative (<i>hera_sim.antpos.HexArray attribute</i>), 39 is_multiplicative (<i>hera_sim.antpos.LinearArray attribute</i>), 40 is_multiplicative (<i>hera_sim.eor.NoiselikeEoR attribute</i>), 41 is_multiplicative (<i>hera_sim.foregrounds.DiffuseForeground attribute</i>), 43 is_multiplicative (<i>hera_sim.foregrounds.PointSourceForeground attribute</i>), 44 </pre>	

is_multiplicative (*hera_sim.noise.ThermalNoise attribute*), 51
 is_multiplicative (*hera_sim.rfi.DTV attribute*), 52
 is_multiplicative (*hera_sim.rfi.Impulse attribute*), 52
 is_multiplicative (*hera_sim.rfi.Scatter attribute*), 53
 is_multiplicative (*hera_sim.rfi.Stations attribute*), 54
 is_multiplicative (*hera_sim.sigchain.Bandpass attribute*), 57
 is_multiplicative (*hera_sim.sigchain.CrossCouplingCrosstalk attribute*), 57
 is_multiplicative (*hera_sim.sigchain.CrossCouplingSpectrum attribute*), 58
 is_multiplicative (*hera_sim.sigchain.Reflections attribute*), 59
 is_multiplicative (*hera_sim.sigchain.WhiteNoiseCrosstalk attribute*), 59

J

jansky_to_kelvin () (*in module hera_sim.utils*), 66
 $\text{Jy2T}()$ (*in module hera_sim.utils*), 64

L

LinearArray (*class in hera_sim.antpos*), 40
 lsts () (*hera_sim.interpolators.Tsky property*), 48
 lsts () (*hera_sim.simulate.Simulator property*), 63
 lsts () (*hera_sim.visibilities.vis_cpu.VisCPU property*), 77

M

meta () (*hera_sim.interpolators.Tsky property*), 48
 module
 hera_sim.antpos, 38
 hera_sim.defaults, 40
 hera_sim.eor, 40
 hera_sim.foregrounds, 41
 hera_sim.interpolators, 44
 hera_sim.io, 48
 hera_sim.noise, 49
 hera_sim.rfi, 51
 hera_sim.sigchain, 54
 hera_sim.simulate, 60
 hera_sim.utils, 63
 hera_sim.vis, 38
 hera_sim.visibilities.conversions, 71
 hera_sim.visibilities.simulators, 67
 hera_sim.visibilities.vis_cpu, 72

N

n_ant (*hera_sim.visibilities.simulators.VisibilitySimulator attribute*), 71
 n_ant (*hera_sim.visibilities.vis_cpu.VisCPU attribute*), 77
 n_beams (*hera_sim.visibilities.simulators.VisibilitySimulator attribute*), 71
 n_beams (*hera_sim.visibilities.vis_cpu.VisCPU attribute*), 77
 n_pix (*hera_sim.visibilities.simulators.VisibilitySimulator attribute*), 71
 n_pix (*hera_sim.visibilities.vis_cpu.VisCPU attribute*), 77
 NoiselikeEoR (*class in hera_sim.eor*), 41
 nside () (*hera_sim.visibilities.simulators.VisibilitySimulator property*), 71
 nside () (*hera_sim.visibilities.vis_cpu.VisCPU property*), 77

P

plot_array () (*hera_sim.simulate.Simulator method*), 62
 point_source_ability (*hera_sim.visibilities.simulators.VisibilitySimulator attribute*), 71
 point_source_ability (*hera_sim.visibilities.vis_cpu.VisCPU attribute*), 77
 PointSourceForeground (*class in hera_sim.foregrounds*), 43

R

Reflections (*class in hera_sim.sigchain*), 58
 refresh () (*hera_sim.simulate.Simulator method*), 62
 resample_Tsky () (*hera_sim.noise.ThermalNoise static method*), 50
 resample_Tsky () (*in module hera_sim.noise*), 49
 RfiStation (*class in hera_sim.rfi*), 52
 rough_delay_filter () (*in module hera_sim.utils*), 66
 rough_fringe_filter () (*in module hera_sim.utils*), 67
 run_sim () (*hera_sim.simulate.Simulator method*), 62

S

Scatter (*class in hera_sim.rfi*), 53
 sim_red_data () (*in module hera_sim.vis*), 38
 simulate () (*hera_sim.visibilities.simulators.VisibilitySimulator method*), 70
 simulate () (*hera_sim.visibilities.vis_cpu.VisCPU method*), 75
 Simulator (*class in hera_sim.simulate*), 60
 sky_noise_jy () (*in module hera_sim.noise*), 49

Stations (*class in hera_sim.rfi*), 53

T

ThermalNoise (*class in hera_sim.noise*), 50
times () (*hera_sim.simulate.Simulator property*), 63
Tsky (*class in hera_sim.interpolators*), 46
tsky () (*hera_sim.interpolators.Tsky property*), 48

U

uvbeam_to_lm() (in module hera_sim.visibilities.conversions), 72

V

validate () (*hera_sim.visibilities.simulators.VisibilitySimulator method*), 70
validate () (*hera_sim.visibilities.vis_cpu.VisCPU method*), 76
vary_gains_in_time () (in module hera_sim.sigchain), 55
vis_cpu () (in module hera_sim.visibilities.vis_cpu), 72
VisCPU (*class in hera_sim.visibilities.vis_cpu*), 73
VisibilitySimulator (*class in hera_sim.visibilities.simulators*), 68

W

white_noise () (in module hera_sim.noise), 50
WhiteNoiseCrosstalk (class in hera_sim.sigchain), 59
write () (*hera_sim.simulate.Simulator method*), 62
write_config_file () (*hera_sim.visibilities.simulators.VisibilitySimulator method*), 70
write_config_file () (*hera_sim.visibilities.vis_cpu.VisCPU method*), 76